


Thomson Reuters ONESOURCE Indirect Tax Compliance SAP S4/HANA Integration

April/2026



Contents

INTEGRATION OVERVIEW	3
INSTALLING INTEGRATION.....	4
IMPORTING TRANSPORT OBJECTS	4
ADDING USER MENU TO A ROLE	5
OAUTH 2.0 Profile Creation.....	7
OAUTH 2.0 Profile Configuration.....	8
RFC Destination Configuration.....	10
RFC configuration set up in OIC Integration	12
CREATING A LOG NUMBER RANGE	13
Extensible Framework.....	14
Features of Extensibility framework.....	22
Use of structures CALC_BSET and CALC_BSEG	23
Enhancement Spots – Badls.....	50
USER GUIDE	51
Download.....	52
Send data to OIC	53
Send data to OIC	54
Download.....	55
Import status.....	58
Log viewer	58
Customize using field mapping.....	60
OIC General Configuration for Field Separator	71
FREQUENTLY ASKED QUESTIONS	73

INTEGRATION OVERVIEW

Thomson Reuters ONESOURCE Indirect Tax Compliance (OIC) integration for SAP is designed to integrate the SAP ERP with OIC with an extensible framework for customers to easily execute the Extraction and Transformation processes and transfer the transactional tax information to the OneSource compliance tool with a user-friendly selection screen.

Key functionalities of this tool include the ability to schedule jobs both in the foreground and background.


Additionally, users can download data for verification and reconciliation purposes, ensuring the accuracy of information sent to OIC. The tool is equipped with an integrated log viewer, enabling users to track uploads directly from SAP screens without the need to log into the OneSource compliance tool separately.

Accessible through a User menu after the installation of the provided transport package, this tool enhances user convenience and efficiency in managing tax compliance processes.

This release version supports G/L Transactions and INTRASTAT reports in EU countries in addition to Value Added Tax (VAT) and Excise Sales List (ESL), and can reconcile INTRASTAT and G/L Transactions reports against VAT-ESL (European Sales List) transactions & SAFT – Report on Thomson Reuters ONESOURCE Indirect Tax Compliance platform.

Supported SAP S/4HANA versions are 2021 & support pack stack (SPS) 6 and onwards.

Architectural diagram



Quick view of Features

FUNCTION	DESCRIPTION
Pre-defined field mapping	This integration offers pre-defined field mapping
Data selection screen	User can use the selection screen to select the required data
Foreground and background scheduling options	User can run this program both in foreground and background
Downloading options to Presentation and Application layer	User can either download to Presentation server or application server
Import status log	User can view the status of the import using import id
Extensible framework with BADIs	BADIs are provided for any customizations
Customizable field mapping with overriding and appending options	Users can add a new field or override an existing mapping. me
Log viewer	Users can view the logs and filter the logs

INSTALLING INTEGRATION

IMPORTING TRANSPORT OBJECTS

Thomson Reuters provided transport will need to be imported into the clients Development system to setup ONESOURCE Indirect Tax Compliance Integration for SAP. All our objects are in the Thomson Reuters Indirect Tax namespace '/TROIC/'. We don't change any customer owned objects. The sequence of transport will be the same for upgrades and new installations.

Transport Package Information


Kindly follow the same sequence of transport as mentioned.

TRANSPORT	DESCRIPTION
GN4K902399	ONESOURCE Indirect Tax Compliance Integration-2.0.0.0 Code
GN4K902400	ONESOURCE Indirect Tax Compliance Integration-2.0.0.0 Conf
GN4K902401	ONESOURCE Indirect Tax Compliance Integration-2.0.0.0 Role


ADDING USER MENU TO A ROLE

For users to be able to access the new ONESOURCE Indirect Tax for SAP setup, configurations, and reports we delivered an SAP User Menu. To access this User Menu, provide your users with the role: /TROIC/USER.


/TROIC/USER contains all the TROIC transactions codes and the full ONESOURCE User Menu. This would normally be given to users that oversee management of the system, configuration, and mapping.



To assign the role to a user, go to Transaction Code SU01. On the Roles Tab, insert the new role name, with start and end dates.



Once the role has been assigned a user can access the User Menu from the main SAP start screen as follows by selecting the **User Menu** icon or **Ctrl+F10**.




OAUTH 2.0 Profile Creation

Users must set up OAuth2.0 profile and RFC configuration to connect SAP to OIC.

Creating OAuth2.0 client profile:

1. Start the object navigator (transaction SE80).
2. Choose Development Object in the dropdown list.
3. To create a development object in the SAP namespace, choose Create -> OAuth 2.0 Client Profile in the context menu of the object name.



1. Enter the object name in the Client Profile field of the popup as 'ZOAUTH_CLIENT' (or any of your preference).
2. Choose the type of service provider as 'DEFAULT'

FS4(1)/800 Create OAuth 2.0 Client Profile

Client Profile: zoauth_client

Type: DEFAULT

- Also, provide the scope as urn:tr:onesource:auth:api:indirecttaxcompliance and activate the client profile.

NOTE: If you have multiple clients in OIC, reach out to Professional services team.

Display OAuth 2.0 Client Profile

Profile: ZOAUTH_CLIENT Saved

Type: DEFAULT

Administration Scopes

SCOPE
urn:tr:onesource:auth:api:indirecttaxcompliance

OAuth 2.0 Profile Configuration

- Go to transaction OA2C_CONFIG to configure the OAuth2.0
- Click on 'Create'.
- Select the OAuth2.0 Client Profile as 'ZOAUTH_CLIENT'.
- Provide the Configuration Name (can be any of your preference) and Client ID given by OIC team.

Create a new OAuth 2.0 client.

OAuth 2.0 Client Profile:

ZOAUTH_CLIENT

Configuration Name:

ZOAUTH_CLIENT

OAuth 2.0 Client ID:

OK

5. Maintain the Client Secret.
6. Also provide the Token Endpoint given by Professional services team.

Details

Administration

Scopes

Enhancement Settings

Created By

TULIOC

Created On

10/26/2023

Created At

07:20:46 PM

Changed By

General Settings

Service Provider Type:

DEFAULT

Profile:

ZOAUTH_OIC

Configuration Name:

ZOAUTH_OIC

OAuth 2.0 Client ID:

OAuth 2.0 Client ID (Internal):

Client Secret:

.....

Authorization Server Settings

Authorization Endpoint:

https://

api

oauth2/v1/token

Token Endpoint:

https://


api

oauth2/v1/token

Revocation Endpoint:

https://

7. Enter the Client Authentication as 'Basic', Resource Access Authentication as 'Header Field' and select grant type as 'Client Credentials'.
8. Click on save. The OAuth2.0 configuration name is 'ZOAUTH_CLIENT'.




The 'Access Settings' dialog box is shown with the following configurations:

- Client Authentication:** ☒ Basic, ☐ Form Fields, ☐ Client Certificate
- Resource Access Authentication:** ☒ Header Field, ☐ Form Field
- Selected Grant Type:** ☐ Current user related, ☐ Resource Owner Password Credentials, ☒ Client Credentials
- Grant Type (Current User related):** ☐ Authorization Code, ☐ SAML 2.0 Bearer Assertion

RFC Destination Configuration

Create RFC Destination

1. Go to transaction SM59 to configure OAuth2.0 2.
2. Click on 'Create'.
3. Enter ZOAUTH_CLIENT_BTP_OIC (or any of your preference) as Destination.
4. In Connection Type select "HTTP connection to external server".



The 'Create Destination' dialog box is shown with the following configurations:

- Destination:** ZOAUTH_CLIENT_BTP_OIC
- Connection Type:** G HTTP connection to external server

5. Enter the host provided by OIC team.
6. Also provide the path prefix /indirect-tax-compliance/v2/imports.

RFC Destination Z0AUTH_CLIENT_BTP_OIC

Connection Test 

RFC Destination	Z0AUTH_CLIENT_BTP_OIC		
Connection Type	G	HTTP Connection to External Server	Description

Description

Description 1	Z0AUTH_CLIENT_BTP_OIC QA SYSTEM
Description 2	
Description 3	

Administration Technical Settings Logon & Security Special Options

Target System Settings

Host	*****cfapps.ap*****hana.ondemand.***	Port	
Path Prefix	/http/indirect-tax-compliance/v2/imports		

HTTP Proxy Options

Global Configuration

Proxy Host	
Proxy Service	
Proxy User	
Proxy PW Status	is initial
Proxy Password	*****

7. In the 'Logon & Security' tab:

Click in 'OAuth Settings' button and enter the values accordingly with Configured in OAuth 2.0 Client.

The Profile should be the same as created before in OAUTH 2.0 Profile Creation and the Configuration should be the same from OAUTH 2.0 Profile Configuration.

Administration Technical Settings Logon & Security Special Options

Logon Procedure

Logon with User

☒ Do not use a user

☐ Basic Authentication

User

PW Status

OAuth Settings

Logon with Ticket

☒ Do not send logon ticket

☐ Send ticket without reference to target system

☐ Send assertion ticket for dedicated target system

System ID Client

FS4(1)/800 OAUTH Settings

Profiles

Configuration

Reject Settings

Select SSL as 'Active' and SSL Certificate select ANONYM SSL (Anonymous).

Administration Technical Settings Logon & Security Special Options

Logon with MQTT/AMQP

User

PW Status

Password

Security Options

Status of Secure Protocol

SSL ☐ Inactive ☒ Active

SSL Certificate Cert. List


☐ Do not use certificate for logon

Authorization for Destination

RFC configuration set up in OIC Integration

To have one or, in case of more than one RFC config point to other/contingencies OIC API systems, you need to configure that in

/TROIC/RFC_CONFIG transaction, as below. Remember to enter the same RFC Destination as created in [Create RFC Destination](#).



Activate the respective RFC destination created in the prior sections. If both lines are active, highest sort order takes precedence for the same username.

Display View "Configuration for RFC API Call": Overview


Configuration for RFC API Call

Sort Order	Active	User Name	RFC Destination
000000	☒	*	Z0AUTH_CLIENT_BTP_OIC
000001	☐	*	OIC_API_CLOUD_QA

CREATING A LOG NUMBER RANGE

The request and response can be logged in SAP in JSON format. Logging can be configured within the Integration setup, and logs can be searched and viewed in SAP using a provided transaction. Review the User Guide section for more details on logging. For logs to be stored with SAP a log number range for Object /TROIC/LOG needs to be setup:

1. Transaction Code /N/TROIC/LOG_NUM_RANGE
2. Press **Change Intervals** to create a new number range interval.



3. Press **Insert Line (F6)** to insert a new line.



4. Make sure that you use a value of 01 for the Number range number. Currently we only support one number range of value 01.
5. Fill out the "From Number and To Number". We recommend opening the number range as wide as possible.

Edit Intervals: OIC Log Counter, Object /TROIC/LOG








	Number Range No.	From No.	To Number	NR Stat
	01	0000000001	9999999999	80

6. SAVE the log number range.

Extensible Framework

Field Mapping

To determine the required OIC target fields, the transaction ‘/TROIC/FIELD_MAP’ is utilized. This transaction facilitates the mapping of the SAP S/4HANA source data tables and to the corresponding target OIC tool fields.

Menu path

Below screenshots represent the S/4HANA to OIC standard field mapping for VAT-ESL, G/L Transactions, INTRASTAT and SAF-T reports.

Below screenshots represent standard mappings for the respective report types.



Display View "Field Mapping for OIC": Overview

Field Mapping for OIC

Standard	Product	Report Type	Sort Order	Active	Entry Grp	CoCd	Source Base	Source Field	Target Field	Comments
☒	OIC	VAT-ESL V...	000010	☒	*	*	BKPF	BUKRS	EntityCode	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000020	☒	*	*	BKPF	BUDAT	ReportingDate	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000030	☒	*	*	BKPF	BUDAT	TransactionDate	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000040	☒	*	*	BKPF	BELNR	TransactionID	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000050	☒	*	*	BKPF	BELNR	InvoiceID	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000060	☒	*	*	BKPF	BKTX	Description	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000070	☒	*	*	CALC_BSEG	INV_TYPE	InvoiceType	LOGICAL VALUE DERIVED FROM BSEG USING KOART AND SHKZG
☒	OIC	VAT-ESL V...	000080	☒	*	*	BKPF	BLDAT	InvoiceDate	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000090	☒	*	*	BKPF	HWAER	Currency	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000100	☒	*	*	BKPF	KURSF	TransactionExRate	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000110	☒	*	*	BKPF	WAERS	TransactionCurrency	CASCADED VALUE FROM BKPF
☒	OIC	VAT-ESL V...	000120	☒	*	*	CALC_BSEG	KOART_APAR	TransactionTypeCode	LOGICAL VALUE DERIVED FROM BSEG USING KOART
☒	OIC	VAT-ESL V...	000130	☒	*	*	CALC_BSEG	KUNNR_NAME	CustomerName	LOGICAL VALUE DERIVED FROM BSEG
☒	OIC	VAT-ESL V...	000140	☒	*	*	CALC_BSEG	SUP_JURID	SupplierJurisdictionID	FIRST 2 CHARACTERS OF SUPPLIER VAT NUMBER
☒	OIC	VAT-ESL V...	000150	☒	*	*	CALC_BSEG	LIFNR_NAME	SupplierName	LOGICAL VALUE DERIVED FROM BSEG
☒	OIC	VAT-ESL V...	000160	☒	*	*	CALC_BSEG	GROSS_AMT	TransactionAmountGross	CALCULATED VALUE FROM BSEG-FWBAS AND BSEG-FWSTE
☒	OIC	VAT-ESL V...	000170	☒	*	*	CALC_BSEG	FWBAS	TransactionAmountNet	DIRECT FIELD WITH DEBIT CREDIT SIGNS
☒	OIC	VAT-ESL V...	000180	☒	*	*	CALC_BSEG	FWSTE	GeneralLedgerAmount	DIRECT FIELD WITH DEBIT CREDIT SIGNS
☒	OIC	VAT-ESL V...	000190	☒	*	*	CALC_BSEG	FWSTE	TransactionAmountTax	DIRECT FIELD WITH DEBIT CREDIT SIGNS
☒	OIC	VAT-ESL V...	000200	☒	*	*	BSET	HKONT	GeneralLedgerAccount	DIRECT FIELD
☒	OIC	VAT-ESL V...	000210	☒	*	*	CALC_BSEG	KBETR	TaxClassificationRate	DIRECT FIELD (ABSOLUTE VALUE)
☒	OIC	VAT-ESL V...	000220	☒	*	*	BSET	MWSKZ	TaxClassificationCode	DIRECT FIELD
☒	OIC	VAT-ESL V...	000230	☒	*	*	CALC_BSEG	SUP_VAT	SupplierVATNumber	FOR AP TRANSACTION, MAPPED TO COMPANY CODE VAT NUMBER ELSE BSET-STCEG
☒	OIC	VAT-ESL V...	000240	☒	*	*	CALC_BSEG	CUST_VAT	CustomerVATNumber	FOR AP TRANSACTION, MAPPED TO COMPANY CODE VAT NUMBER ELSE BSET-STCEG
☒	OIC	VAT-ESL V...	000250	☒	*	*	BSET	STCEG	TaxNumber	DIRECT FIELD
☒	OIC	VAT-ESL V...	000260	☒	*	*	CALC_BSEG	CUST_JURID	CustomerJurisdictionID	FIRST 2 CHARACTERS OF CUSTOMER VAT NUMBER
☒	OIC	VAT-ESL V...	000270	☒	*	*	BSET	KTOSL	TransactionKey	TRANSACTION KEY

Field Mapping for OIC

Standard	Product	Report Type	Sort Order	CoCd	Source Base	Source Field	Target Field	Comments
☒	OIC	GL-T GL-TR	000010	*	BKPF	BUKRS	EntityCode	CASCADED VALUE FROM BKPF
☒	OIC	GL-T GL-TR	000020	*	BSET	HKONT	GeneralLedgerAccount	DIRECT FIELD
☒	OIC	GL-T GL-TR	000030	*	CALC_BSEG	FWSTE	GeneralLedgerAmount	DIRECT FIELD WITH DEBIT CREDIT SIGNS
☒	OIC	GL-T GL-TR	000040	*	BKPF	BLDAT	InvoiceDate	CASCADED VALUE FROM BKPF
☒	OIC	GL-T GL-TR	000050	*	BKPF	BELNR	InvoiceID	CASCADED VALUE FROM BKPF
☒	OIC	GL-T GL-TR	000060	*	BSEG	HBUDAT	PostingDate	CASCADED VALUE FROM BKPF
☒	OIC	GL-T GL-TR	000070	*	BSET	MLDDT	ReportingDate	CASCADED VALUE FROM BKPF
☒	OIC	GL-T GL-TR	000080	*	BSET	MWSKZ	TaxClassificationCode	DIRECT FIELD
☒	OIC	GL-T GL-TR	000090	*	CALC_BSEG	FWBAS	TransactionAmountNet	DIRECT FIELD WITH DEBIT CREDIT SIGNS
☒	OIC	GL-T GL-TR	000100	*	CALC_BSEG	FWSTE	TransactionAmountTax	DIRECT FIELD WITH DEBIT CREDIT SIGNS
☒	OIC	GL-T GL-TR	000110	*	CALC_BSEG	KOART_APAR	TransactionTypeCode	LOGICAL VALUE DERIVED FROM BSEG USING KOART

Field Mapping for OIC								
Standard	Product	Report Type	Sort Order	CoCd	Source Base	Source Field	Target Field	Comments
☒	OIC	INTRASTAT	▼ 000010	*	/ECRS/RPIT	PTVAT	CustomerVATNumber	
☒	OIC	INTRASTAT	▼ 000020	*	/ECRS/RPIT	PTCTI	DestinationJurisdictionID	
☒	OIC	INTRASTAT	▼ 000030	*	/ECRS/RPIT	INCZO	DestinationRegionArrival	
☒	OIC	INTRASTAT	▼ 000040	*	/ECRS/POIA	BUKRS	Entitycode	
☒	OIC	INTRASTAT	▼ 000050	*	/ECRS/CALC_R.DIREC		Flow	
☒	OIC	INTRASTAT	▼ 000060	*	/ECRS/RPIT	MAKTX	GoodsDescription	
☒	OIC	INTRASTAT	▼ 000070	*	/ECRS/RPIT	MOTAB	ModeTransport	
☒	OIC	INTRASTAT	▼ 000080	*	/ECRS/RPIT	BTTYP	NatureTransaction	DIRECT
☒	OIC	INTRASTAT	▼ 000090	*	/ECRS/RPIT	CTOOI	OriginArrivalJurisdictionID	
☒	OIC	INTRASTAT	▼ 000100	*	/ECRS/RPHD	RPCTY	OriginJurisdictionID	
☒	OIC	INTRASTAT	▼ 000110	*	/ECRS/RPIT	REGIN	OriginRegionDispatch	
☒	OIC	INTRASTAT	▼ 000120	*	/ECRS/CALC_R.PORTI_LO		PortLoading	
☒	OIC	INTRASTAT	▼ 000130	*	/ECRS/CALC_R.PORTI_UN		PortUnloading	
☒	OIC	INTRASTAT	▼ 000140	*	/ECRS/CALC_R.LCHTS		ReportingDate	
☒	OIC	INTRASTAT	▼ 000150	*	/ECRS/RPIT	SPQUA	SupplementaryQuantity	
☒	OIC	INTRASTAT	▼ 000160	*	/ECRS/RPIT	COMCD	CommodityCode	
☒	OIC	INTRASTAT	▼ 000170	*	/ECRS/RPIT	INCOI	DeliveryTermsFirstSub	
☒	OIC	INTRASTAT	▼ 000180	*	/ECRS/RPIT	ITQUA	Quantity	
☒	OIC	INTRASTAT	▼ 000190	*	/ECRS/CALC_R.INVAL		TransactionAmountNet	
☒	OIC	INTRASTAT	▼ 000200	*	/ECRS/RPIT	STVAL	TransactionStatisticalValue	
☒	OIC	INTRASTAT	▼ 000210	*	/ECRS/CALC_R.DIREC		TransactionTypeCode	
☒	OIC	INTRASTAT	▼ 000220	*	/ECRS/CALC_R.INVAL		ValueSupplyLocalCurrency	DIRECT FIELD WITH DEBIT CREDIT SIGNS

Display View "Maintain Dynamic Field Mapping": Overview									
Maintain Dynamic Field Mapping									
Standard	Product	Report Type	Country	Sort Order	Active	CoCd	Source Base	Source Field	Target Field
☒	OIC	SAFT-ASSETS	▼ RO	000010	☒	*	ANLA	BUKRS	ENTITYCODE
☒	OIC	SAFT-ASSET TRANSACTIONS	▼ RO	000010	☒	*	SKB1	BUKRS	ENTITYCODE
☒	OIC	SAFT-ANALYSIS TYPE TABLE	▼ RO	000010	☒	*	COMPANY_CODE	BUKRS	ENTITYCODE
☒	OIC	SAFT-CUSTOMERS	▼ RO	000010	☒	*	KNB1	BUKRS	ENTITYCODE
☒	OIC	SAFT-GL ACCOUNTS	▼ RO	000010	☒	*	SKB1	BUKRS	ENTITYCODE
☒	OIC	SAFT-GENERAL LEDGER ENTRIES	▼ RO	000010	☒	*	BKPF	BUKRS	ENTITYCODE
☒	OIC	SAFT-MOVEMENT TYPE TABLE	▼ RO	000010	☒	*	COMPANY_CODE	BUKRS	ENTITYCODE
☒	OIC	SAFT-MOVEMENT OF GOODS	▼ RO	000010	☒	*	BKPF	BUKRS	ENTITYCODE
☒	OIC	SAFT-OWNERS	▼ RO	000010	☒	*	LFBI	BUKRS	ENTITYCODE
☒	OIC	SAFT-PAYMENTS	▼ RO	000010	☒	*	BSEG	BUKRS	ENTITYCODE
☒	OIC	SAFT-PURCHASE INVOICES	▼ RO	000010	☒	*	BKPF	BUKRS	ENTITYCODE
☒	OIC	SAFT-PRODUCTS	▼ RO	000010	☒	*	COMPANY_CODE	BUKRS	ENTITYCODE
☒	OIC	SAFT-PHYSICAL STOCK	▼ RO	000010	☒	*	COMPANYCODE	BUKRS	ENTITYCODE
☒	OIC	SAFT-SALES INVOICES	▼ RO	000010	☒	*	BSEG	BUKRS	ENTITYCODE
☒	OIC	SAFT-SUPPLIERS	▼ RO	000010	☒	*	LFBI	BUKRS	ENTITYCODE
☒	OIC	SAFT-TAX TABLE	▼ RO	000010	☒	*	COMPANYCODE	BUKRS	ENTITYCODE

Below are the Tables & CDS view used in each data set for SAFT- Report

Dataset	Tables	CDS Views
SAFT- GLA	SKB1	/TROIC/SKB1_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
	SKAT	/TROIC/SKAT_CDS
	No compatible table available	V_FAGLFLEX_VIEW
SAFT- CUS	KNA1	/TROIC/KNA1_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
	ADRC	/TROIC/ADRC_CDS
	KNB1	/TROIC/KNB1_CDS
	SKB1	/TROIC/SKB1_CDS
	KNC1	/TROIC/KNC1_CDS
	KNBK	/TROIC/KNBK_CDS

	TIBAN	/TROIC/TIBAN_CDS
	BNKA	/TROIC/BNKA_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
SAFT-SUP	LFB1	/TROIC/LFB1_CDS
	BUT000	/TROIC/BUT000_CDS
	CVI_VEND_LINK	/TROIC/CVI_VEND_LINK_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
	ADRC	/TROIC/ADRC_CDS
	LFA1	/TROIC/LFA1_CDS
	LFBK	/TROIC/LFBK_CDS
	TIBAN	/TROIC/TIBAN_CDS
	LFC1	/TROIC/LFC1_CDS
	BNKA	/TROIC/BNKA_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
SAFT - UOM	/TROIC/D_UOMMAP	/TROIC/UOMMAP_CDS
SAFT - TAX	/TROIC/SAFT_TAX	/TROIC/SAFT_TAX_CDS
	T007A	We are using the table directly.
	T005	We are using the table directly.
SAFT - ATT	/TROIC/D_ANLTYP	/TROIC/ANLTYP_CDS
	TKA02	/TROIC/TKA02_CDS
	CSKT	/TROIC/CSKT_CDS
	CEPCT	/TROIC/CEPCT_CDS
	PROJ	/TROIC/PROJ_CDS
	T001W	/TROIC/T001W_CDS
	T001K	/TROIC/T001K_CDS
	TVK0	/TROIC/TVKO_CDS
	TVTWT	/TROIC/TVTWT_CDS
	TVKOV	/TROIC/TVKOV_CDS
SAFT-MTT	T156	/TROIC/T156_CDS

	/TROIC/D_MVTYP	/TROIC/MVTYP_CDS
SAFT-PRD	T134	/TROIC/T134_CDS
	MVKE	/TROIC/MVKE_CDS
	MAKT	/TROIC/MAKT_CDS
	T179	/TROIC/T179_CDS
	MARA	/TROIC/MARA_CDS
	T006A	/TROIC/T006A_CDS
	TVKO	/TROIC/TVKO_CDS
	MARM	/TROIC/MARM_CDS
	MBEW	/TROIC/MBEW_CDS
	/TROIC/D_UOMMAP	/TROIC/UOMMAP_CDS
	T001K	/TROIC/T001k_CDS
	T001W	/TROIC/T001W_CDS
	MARC	/TROIC/MARC_CDS
SAFT - PST	T001K	/TROIC/T001K_CDS
	T001W	/TROIC/T001W_CDS
	MARA	/TROIC/MARA_CDS
	MARM	/TROIC/MARM_CDS
	MARC	/TROIC/MARC_CDS
	MBEW	/TROIC/MBEW_CDS
	MBEWH	/TROIC/MBEWH_CDS
	MARD	/TROIC/MARD_CDS
	KNA1	/TROIC/KNA1_CDS
	LFA1	/TROIC/LFA1_CDS
	/TROIC/D_STKCH	/TROIC/STKCH_CDS
	/TROIC/D_UOMMAP	/TROIC/UOMMAP_CDS
SAFT-OWN	LFB1	/TROIC/LFB1_CDS
	BUT000	/TROIC/BUT000_CDS
	CVI_VEND_LINK	/TROIC/CVI_VEND_LINK_CDS

	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
	LFA1	/TROIC/LFA1_CDS
	LFBK	/TROIC/LFBK_CDS
	TIBAN	/TROIC/TIBAN_CDS
	BNKA	/TROIC/BNKA_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
SAFT-GLE	BSEG	/TROIC/BSEG_CDS
	BKPF	/TROIC/BKPF_CDS
	BSET	/TROIC/BSET_CDS
	KNA1	/TROIC/KNA1_CDS
	LFA1	/TROIC/LFA1_CDS
	T003T	/TROIC/T003T_CDS
	VRBK	/TROIC/VRBK_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
	BUT000	/TROIC/BUT000_CDS
	CVI_VEND_LINK	/TROIC/CVI_VEND_LINK_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
SAFT-SIN	BSEG	/TROIC/BSEG_CDS
	BKPF	/TROIC/BKPF_CDS
	BSET	/TROIC/BSET_CDS
	SKB1	/TROIC/SKB1_CDS
	VRBK	/TROIC/VRBK_CDS
	VRBP	/TROIC/VRBP_CDS
	KNA1	/TROIC/KNA1_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
	ADRC	/TROIC/ADRC_CDS
	PRCD_ELEMENTS	/TROIC/PRCD_ELM_CDS
	T001W	/TROIC/T001W_CDS
	/TROIC/SAFT_TAX	/TROIC/SAFT_TAX_CDS

	/TROIC/D_DOCTYP	/TROIC/DOCTYP_CDS
	MKPF	/TROIC/MKPF_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
	VBFA	/TROIC/VBFA_CDS
SAFT-PIN	BSEG	/TROIC/BSEG_CDS
	BKPF	/TROIC/BKPF_CDS
	BSET	/TROIC/BSET_CDS
	BUT000	/TROIC/BUT000_CDS
	CVI_VEND_LINK	/TROIC/CVI_VEND_LINK_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
	LFA1	/TROIC/LFA1_CDS
	ADRC	/TROIC/ADRC_CDS
	RBKP	/TROIC/RBKP_CDS
	RSEG	/TROIC/RSEG_CDS
	EKPO	/TROIC/EKPO_CDS
	SKB1	/TROIC/SKB1_CDS
	/TROIC/SAFT_TAX	/TROIC/SAFT_TAX_CDS
	/TROIC/D_DOCTYP	/TROIC/DOCTYP_CDS
	T001W	/TROIC/T001W_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
	MSEG	/TROIC/MSEG_CDS
SAFT - PAY	BSEG	/TROIC/BSEG_CDS
	BKPF	/TROIC/BKPF_CDS
	BSET	/TROIC/BSET_CDS
	KNA1	/TROIC/KNA1_CDS
	LFA1	/TROIC/LFA1_CDS
	/TROIC/D_PAYMCH	/TROIC/PAYMCH_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
	T059Z	/TROIC/T059Z_CDS

	/TROIC/SAFT_TAX	/TROIC/SAFT_TAX_CDS
	WITH_ITEM	/TROIC/WITH_ITEM_CDS
	BUT000	/TROIC/BUT000_CDS
	CVI_VEND_LINK	/TROIC/CVI_VEND_LINK_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
SAFT-MVG	BSEG	/TROIC/BSEG_CDS
	BKPF	/TROIC/BKPF_CDS
	MKPF	/TROIC/MKPF_CDS
	MSEG	/TROIC/MSEG_CDS
	ADRC	/TROIC/ADRC_CDS
	BSET	/TROIC/BSET_CDS
	T007A	/TROIC/T007A_CDS
	ISEG	/TROIC/ISEG_CDS
	KNA1	/TROIC/KNA1_CDS
	LFA1	/TROIC/LFA1_CDS
	MARM	/TROIC/MARM_CDS
	MARA	/TROIC/MARA_CDS
	RSEG	/TROIC/RSEG_CDS
	/TROIC/D_UOMMAP	/TROIC/UOMMAP_CDS
	/TROIC/D_MVTYP	/TROIC/MVTYP_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
	T003T	/TROIC/T003T_CDS
	BUT000	/TROIC/BUT000_CDS
	CVI_VEND_LINK	/TROIC/CVI_VEND_LINK_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
SAFT - AST	ANLA	/TROIC/ANLA_CDS
	T095	/TROIC/T095_CDS
	ANLB	/TROIC/ANLB_CDS
	LFA1	/TROIC/LFA1_CDS

	ACDOCA	/TROIC/ACDOCA_CDS
	T093C	/TROIC/T093C_CDS
	T090NAZ	/TROIC/T090NAZ_CDS
	T090NS	/TROIC/T090NS_CDS
	/TROIC/D_GL_ACC	/TROIC/GL_ACC_CDS
	/TROIC/D_CTLOG	/TROIC/CTLOG_CDS
	BUT000	/TROIC/BUT000_CDS
	CVI_VEND_LINK	/TROIC/CVI_VEND_LINK_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
SAFT- ATR	LFA1	/TROIC/LFA1_CDS
	BUT000	/TROIC/BUT000_CDS
	CVI_VEND_LINK	/TROIC/CVI_VEND_LINK_CDS
	DFKKBPTAXNUM	/TROIC/DFKKBPTAXNUM_CDS
	ACDOCA	/TROIC/ACDOCA_CDS
	/TROIC/D_ASTTYP	/TROIC/ASTTYP_CDS
	TABW	/TROIC/TABW_CDS
	/TROIC/D_ATRCFG	/TROIC/ATRCFG_CDS
	ANLA	/TROIC/ANLA_CDS

Features of Extensibility framework

1. Users can use this framework to view the field mapping delivered as well as customize the field mapping based on the customer specific requirements by creating a custom entry with a highest sort order either to override pre-defined mapping or to add a new mapping.
2. Users have the capability to either activate or deactivate using 'Active' Check box and to restrict the mapping for a specific company code using 'CoCd'.
3. Data extraction for VAT-ESL and G/L Transactions report is performed by leveraging BSET entries and incorporating other relevant values from either BKPF, BSEG using CDS views /TROIC/BKPF_DDF, /TROIC/BSEG, /TROIC/BSET and for INTRASTAT report it is performed using /ECRS/POIA - Provider of Information (Countries), /ECRS/RPHD - INTRASTAT Declaration Header Data, /ECRS/RPIT - INTRASTAT Declaration Item Data tables using CDS views /TROIC/RPHD_CDS, /TROIC/ECRS_ITEM, /TROIC/ECRS_POIA for the corresponding report.

4. Data Extraction for SAFT Report is performed using the report types as below:
 - SAFT- General Ledger Accounts
 - SAFT - Customers
 - SAFT - Suppliers
 - SAFT - Assests
 - SAFT - UOM Table
 - SAFT - Tax Table
 - SAFT - Analysis Type Table
 - SAFT - Movement Type Table
 - SAFT - Products
 - SAFT - Physical Stock
 - SAFT - Owners
 - SAFT - General Ledger Entries
 - SAFT - Sales Invoices
 - SAFT - Purchase Invoices
 - SAFT - SD Payments
 - SAFT - Assets Transactions
 - SAFT - Movement of Goods
5. Except for mappings labeled 'DIRECT FIELD' in the comments section, all others incorporate a defined logic for transferring values to the target. The label 'DIRECT FIELD' indicates that the value has been directly mapped from the standard SAP S/4HANA source table to the OIC application target field without any manipulation.
6. The label 'CASCADED VALUE' signifies that the entry from the source table is manipulated across multiple lines of BSET, BSEG, /ECSR/RPHD, /ECSR/RPIT.
7. The column 'Standard' is utilized to indicate that a mapping line is part of the pre-delivered standard mapping provided by Thomson Reuters.

Refer the section for customizing instructions.

Use of structures CALC_BSET and CALC_BSEG

We created structures, CALC_BSEG and CALC_BSET for VAT-ESL and G/L Transactions, /TROIC/RPHD_CALC_S and /TROIC/RPIT_CALC_S for INTRSTAT reports specifically designed for field mapping. These structures are filled up in standard Thomson Reuters code, intended to accommodate any necessary calculations and data manipulations during the field mapping process.

- TROIC/SAFT_BALANCES_S – used in SAFT Supplier, GLA & Customer Dataset (to calculate the amount and holds the balance related data).

Dictionary: Display Structure

Structure: /TROIC/SAFT_BALANCES_S Active

Short Description: SAFT BALANCES Structure

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 5

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
OP_DB	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
OP_CD	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CL_DB	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CL_CD	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STCEG	Types	STCEG	CHAR	20	0		0 VAT Registration Number

- /TROIC/SAFT_VAT_S – used in SAFT - Customers, Supplier, Owners, Sales & Purchase Invoice Datasets, (conversion of VAT numbers to country's VAT Number, Credit & Debit Indicator for Transactional Data)

Structure: /TROIC/SAFT_VAT_S Active

Short Description: SAFT Additional Calculation fields

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 4

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
STCEG	Types	STCEG	CHAR	20	0		0 VAT Registration Number
STCEG_KUNNR	Types	STCEG	CHAR	20	0		0 VAT Registration Number
STCEG_LIFNR	Types	STCEG	CHAR	20	0		0 VAT Registration Number
CD_INDICATOR	Types	CHAR1	CHAR	1	0		0 Single-Character Flag

- /TROIC/SAFT_CALC_STOCK_S - used in SAFT Physical Stock (to calculate the Opening & Closing – Stock Value & Stock Quantity)

Structure	/TROIC/SAFT_CALC_STOCK_S		Active
Short Description	SAFT Stock calculations structure		
AttributesComponentsInput Help/CheckCurrency/quantity fields			
<			

- /TROIC/CALC_ANL_TYP - used in SAFT Analysis Type Table (to gather all the SAP analysis types (CC, PC, PROJ, BRANCH) to the single structure & give it as the input to the field mapping

Structure

/TROIC/CALC_ANL_TYP

Active

Short Description

Structure for analysis type

Attributes

Components

Input Help/Check

Currency/quantity fields



Built-In Type

1 / 9

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
BUKRS	Types	▼ BUKRS	CHAR	4	0		0 Company Code
ANL_TYP	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ANL_DESC	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ANL_ID	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ANL_ID_DESC	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
NETWR	Types	▼ NETWR	CURR	15	2		0 Net Value in Document Currency
ANL_AMT	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ANL_CURR_COD	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ANL_CURR_AMT	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

- /TROIC/SAFT_CALC_AMOUNTS – used in SAFT GLE Dataset (to calculate the Amounts in Local & Reporting Country)

Dictionary: Display Structure

</

- /TROIC/SAFT_CALC_MVG – used in SAFT MVG Dataset (for conversion of Unit of Measurements)

Dictionary: Display Structure

Structure: /TROIC/SAFT_CALC_MVG Active

Short Description: SAFT Calculation substructure for MVG

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 4

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
UOMCONVESRIONFACT	Types	▼ /TROIC/UOMCONVE...	DEC	5	2		0 UOMtoUOM conversion factor
CURRENCYAMOUNT	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
MOVEMENT_REF	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
DOC_TYP	Types	▼ /TROIC/CHAR18	CHAR	18	0		0 data element for 18 char

- /TROIC/SAFT_CALC_PRD – used in SAFT PRD Dataset (for conversion of Unit of Measurements)

Dictionary: Display Structure

Structure: /TROIC/SAFT_CALC_PRD Active

Short Description: SAFT Calculation substructure for PRD

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 3

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
UOMCONVESRIONFA...	Types	▼ /TROIC/UOMCONVE...	DEC	5	2		0 UOMtoUOM conversion factor
UOM_BASE	Types	▼ MSEHI	UNIT	3	0		0 Unit of Measurement
UOM_STANDARD	Types	▼ MEINS	UNIT	3	0		0 Base Unit of Measure

- /TROIC/SAFT_SELECT_PARAM: It's a Global Structure that holds all the selection screen parameters of all SAFT Data sets.

Dictionary: Display Structure

Structure: /TROIC/SAFT_SELECT_PARAM Active

Short Description: SAFT selection parameters structure

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 20

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
BUKRS	Types	BUKRS	CHAR	4	0	0	0 Company Code
SAKNR	Types	SAKNR	CHAR	10	0	0	0 G/L Account Number
ALTKT	Types	ALTKT	CHAR	10	0	0	0 Account Number in Group
C_GL	Types	BOOLEAN	CHAR	1	0	0	0 Boolean Variable (X = True, - = False, Space = Unknown)
GJAHR	Types	GJAHR	NUMC	4	0	0	0 Fiscal Year
MONAT	Types	MONAT	NUMC	2	0	0	0 Fiscal period
RLDNR	Types	RLDNR	CHAR	2	0	0	0 Ledger
BUKRS_RANGE	Types	FUDY_BUKRS_RANGE	III	0	0	0	0 Range table of Company Code
POSTING_DATES	Types	/TROIC/POSTING...	III	0	0	0	0 SAFT Posting dates range
POSTING_DATES_R...	Types	RANGE_DATE	III	0	0	0	0 Structure of a Range Table for a Date
C_CUS	Types	BOOLEAN	CHAR	1	0	0	0 Boolean Variable (X = True, - = False, Space = Unknown)
KUNNR	Types	KUNNR	CHAR	10	0	0	0 Customer Number
AKONT	Types	AKONT	CHAR	10	0	0	0 Reconciliation Account in General Ledger
C_UOM	Types	BOOLEAN	CHAR	1	0	0	0 Boolean Variable (X = True, - = False, Space = Unknown)
C_SUP	Types	BOOLEAN	CHAR	1	0	0	0 Boolean Variable (X = True, - = False, Space = Unknown)
LIFNR	Types	LIFNR	CHAR	10	0	0	0 Account Number of Supplier
C_MIT	Types	BOOLEAN	CHAR	1	0	0	0 Boolean Variable (X = True, - = False, Space = Unknown)
C_ATR	Types	BOOLEAN	CHAR	1	0	0	0 Boolean Variable (X = True, - = False, Space = Unknown)

- /TROIC/SAFT_CALC_AST – This structure is used in SAFT_AST dataset (to calculate amounts for the assets).

Structure: /TROIC/SAFT_CALC_AST Active

Short Description: calculation structure for SAFT - Asset

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 21

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ASTVALUETYP	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
AQ_PRD_COST_BGN	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
AQ_PRD_COST_END	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
INVEST_SUPRT	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
TRANSFERS	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
BOOK_VLU_BGN	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
DEP_FOR_PERIOD	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
APR_FOR_PERIOD	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
EXT_DEP METH	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
EXT_DEP AMT PER...	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
ACC_DEP	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
BOOK_VLU_END	Types	FINS_VHCUR12	CURR	23	2	0	0 Amount in Company Code Currency
DT_OF_AQUISITION	Types	BZDAT_PN	DATS	8	0	0	0 Prima Nota Information for BZDAT
SUPPLIERID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ACCOUNTID	Types	/TROIC/STACCID	CHAR	35	0	0	0 SAFT Standard Account ID
VALUATION_CLASS	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ASSET_YEAR	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ASSET_MONTH	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects

- /TROIC/SAFT_CALC_ATR – The structure is used in SAFT_ATR dataset (it is used for calculating asset transactions).

Structure	/TROIC/SAFT_CALC_ATR		Active
Short Description	Structure for asset transaction calculations		
AttributesComponentsInput Help/CheckCurrency/quantity fields			
</			

- /TROIC/SAFT_CALC_PIN – This structure is used in SAFT_PIN dataset (it is used to calculate amount in purchase invoice dataset).

Structure	/TROIC/SAFT_CALC_PIN		Active			
Short Description	SAFT Calculation structure for PIN					
AttributesComponentsInput Help/CheckCurrency/quantity fields						
Built-In Type 1 / 6						
Component	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
TAX_AMT_LOCAL	DMBTR	CURR	23	2		0 Amount in local currency
TAX_AMT_DOCU	WRBTR	CURR	23	2		0 Amount in document currency
GROSS_TOTAL	DMBTR	CURR	23	2		0 Amount in local currency
DELIVERY_DATE	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
DELIVERY_TODATE	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
DELIVERY_FROMDA...	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

- /TROIC/SAFT_CALC_SIN – This structure is used in SAFT_SIN dataset (it is used to calculate the net value for the sales invoice).

Structure	/TROIC/SAFT_CALC_SIN		Active				
Short Description	SAFT Calculation Structure for SIN						
Attributes	Components	Input Help/Check	Currency/quantity fields				
 Built-In Type 1 / 5							
Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
UNIT_PRICE	Types	▼ NETWR_FP	CURR	15	2		0 Net Value of Billing item in Document Currency
DELIVERY_DATE	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
DELIVERY_FROMDA...	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
DELIVERY_TODATE	Types	▼ /TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
INVOICE_LINEAMT	Types	▼ NETWR	CURR	15	2		0 Net Value in Document Currency

SAFT CUSTOM TABLES

We have created custom tables, where we can configure the data as per the SAFT requirement.

SAFT Dataset - Analysis Type Table

- /TROIC/D_ANLTYP: This table is used to maintain the Analysis types against each company code.
- View Name - /TROIC/V_ANLTYPE - Maintenance created on top of the custom table /TROIC/D_ANLTYP.
- T – code - /TROIC/SAFT_ANLTYP.

Transparent Table

/TROIC/D_ANLTYP

Active

Short Description

Analysis Type Table

Attributes

Delivery and Maintenance

Fields

Input Help/Check

Currency/Quantity Fields

Indexes

Srch Help

Built-In Type

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
MANDT	☒	☒	MANDT	CLNT	3	0		0 Client
BUKRS	☒	☒	BUKRS	CHAR	4	0		0 Company Code
ANALS_TYP	☒	☒	/TROIC/ANLSTY	CHAR	3	0		0 Analysis Type
COUNTRY	☐	☐	/TROIC/COUNTRY	CHAR	3	0		0 Country
COUNTRY_GROUP	☐	☐	/TROIC/COUNTRY_GROUP	CHAR	4	0		0 Country Group
DES	☐	☐	/TROIC/DES	CHAR	35	0		0 Description

Maintenance View

/TROIC/V_ANLTYPE

Active

Short Description

Analysis Type

Attributes

Table/Join Conditions

View Fields


Selection Conditions

Maint.Status

Table fields

View field	Table	Field	P Key	Data elem.	M...	DType	Length	Short description
MANDT	/TROIC/D_ANLTYP	MANDT	☒	MANDT	☐	CLNT	3	Client
BUKRS	/TROIC/D_ANLTYP	BUKRS	☒	BUKRS	☐	CHAR	4	Company Code
ANALS_TYP	/TROIC/D_ANLTYP	ANALS_TYP	☒	/TROIC/ANLSTY	☐	CHAR	3	Analysis Type
COUNTRY	/TROIC/D_ANLTYP	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/D_ANLTYP	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
DES	/TROIC/D_ANLTYP	DES	☐	/TROIC/DES	☐	CHAR	35	Description

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "Analysis Type": Overview

New Entries

CoCd	Analysis ...	Description
0MB1	CC	COST CENTER
2610	PC	PROFIT CENTER
2810	CC	COST CENTRE
2810	PC	PROFIT CENTRE
2810	PL	PLANT
2810	PRJ	PROJECT
2810	SLS	DISTRIBUTION CHANNEL
2820	CC	COST CENTRE
2820	PC	PROFIT CENTRE
2820	PL	PLANT
2820	PRJ	PROJECT
2820	SLS	DISTRIBUTION CHANNEL

SAFT Dataset - Purchase Invoices & Sales Invoices Data.

- Table Name - /TROIC/D_DOCTYP: This table is used to maintain the SAP Document type (whichever the client uses) to country's document type.
- View Name - /TROIC/V_DOCTYPE Maintenance created on top of the custom table /TROIC/D_DOCTYP.
- T - code - /TROIC/SAFT_DOCTYP

Transparent Table **/TROIC/D_DOCTYP** Active

Short Description Invoice Doc Types - SAFT Doc Types Mapping

Attributes Delivery and Maintenance **Fields** Input Help/Check Currency/Quantity Fields Indexes

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
MANDT	☒	☒	MANDT	CLNT	3	0	0	Client
BLART	☒	☒	BLART	CHAR	2	0	0	Document Type
COUNTRY	☐	☐	/TROIC/COUNTRY	CHAR	3	0	0	Country
COUNTRY_GROUP	☐	☐	/TROIC/COUNTRY ...	CHAR	4	0	0	Country Group
SAFT_INV_CD	☐	☐	/TROIC/SAFT_INV...	CHAR	3	0	0	SAFT Invoice Code


Maintenance View **/TROIC/V_DOCTYP** Active

Short Description Invoice Document Type

Attributes Table/Join Conditions **View Fields** Selection Conditions Maint.Status

View field	Table	Field	P Key	Data elem.	M...	DTyp	Length	Short description
MANDT	/TROIC/D_DOCTYP	MANDT	☒	MANDT	☐	CLNT	3	Client
BLART	/TROIC/D_DOCTYP	BLART	☒	BLART	☐	CHAR	2	Document Type
COUNTRY	/TROIC/D_DOCTYP	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/D_DOCTYP	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
SAFT_INV_CD	/TROIC/D_DOCTYP	SAFT_INV_CD	☐	/TROIC/SAFT_INV_CD	☐	CHAR	3	SAFT Invoice Code

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "Invoice Document Type": Overview				
	New Entries			
Invoice Document Type				
Type	Country	Cntry Grp	Inv Code	
AB	RO	*	385	▼
DG	RO	*	Credit Note	▼
DR	RO	*	Invoice	▼
RE	RO	*	Self-Invoice	▼
RV	RO	*	Corrected Invoice	▼
SA	RO	*	385	▼

SAFT Dataset - GLA data

- Table Name - /TROIC/D_GL_ACC - This table is used to maintain the account type for each GL – Active, Passive or Bifunctional.
- View Name - /TROIC/V_GLACC - Maintenance created on top of the custom table /TROIC/D_GL_ACC.
- T-Code - /TROIC/SAFT_GL_ACC

Transparent Table

/TROIC/D_GL_ACC

Active

Short Description

GL Accounts

Attributes

Delivery and Maintenance

Fields

Input Help/Check

Currency/Quantity Fields

Indexes

Srch Help


Built-In Type

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
MANDT	☒	☒	MANDT	CLNT	3	0		0 Client
KTOPL	☒	☒	KTOPL	CHAR	4	0		0 Chart of Accounts
SAKNR	☒	☒	SAKNR	CHAR	10	0		0 G/L Account Number
COUNTRY	☐	☐	/TROIC/COUNTRY	CHAR	3	0		0 Country
COUNTRY_GROUP	☐	☐	/TROIC/COUNTRY ...	CHAR	4	0		0 Country Group
STACCID	☐	☐	/TROIC/STACCID	CHAR	35	0		0 SAFT Standard Account ID
ACT_TYP	☐	☐	/TROIC/ACCTYPE	NUMC	2	0		0 Account Type

Maintenance View	/TROIC/V_GLACC	Active
Short Description	GL Accounts	
Attributes	Table/Join Conditions	View Fields
Selection Conditions	Maint.Status	

View field	Data elem.	M...	DType	Length	Short description
MANDT	MANDT	☐	CLNT	3	Client
KTOPL	KTOPL	☐	CHAR	4	Chart of Accounts
SAKNR	SAKNR	☐	CHAR	10	G/L Account Number
COUNTRY	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
STACCID	/TROIC/STACCID	☐	CHAR	35	SAFT Standard Account ID
ACT_TYP	/TROIC/ACCTYPE	☐	NUMC	2	Account Type
		☐			

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "GL Accounts": Overview					
      					
GL Accounts					
Chrt/Accts	G/L Account	Country	Cntry Grp	Standard Account ID	Acc Typ
YCOA	192700	RO	*	151	Activ
YCOA	701100	RO	*	7015	Activ
YCOA	884000	RO	*	7588	Activ
YCOA	10010000	RO	*	5311	Activ
YCOA	10020000	RO	*	5311	Activ
YCOA	11001000	RO	*	5121	Activ
YCOA	11001010	RO	*	5121	Activ
YCOA	11001020	RO	*	5121	Activ
YCOA	11001030	RO	*	5125	Activ
YCOA	11001040	RO	*	5121	Activ
YCOA	11001045	RO	*	5121	Activ
YCOA	11001050	RO	*	5121	Activ
YCOA	11001055	RO	*	5121	Activ
YCOA	11001060	RO	*	5121	Activ
YCOA	11001065	RO	*	5121	Activ
YCOA	11001066	RO	*	5121	Activ
YCOA	11001067	RO	*	5121	Activ
YCOA	11001070	RO	*	5125	Activ

SAFT Dataset - Physical Stock

- Table Name - /TROIC/D_STKCH: This Table holds the material and company code and its stock characteristic (like which type of material it is handling).
 - View Name - /TROIC/V_STKCHAR: Maintenance created on top of the custom table /TROIC/D_STKCH.
 - T – code - /TROIC/SAFT_STKCH.

Transparent Table

/TROIC/D_STKCH

Active

Short Description

Table for Stock Characteristic and its value

Attributes

Delivery and Maintenance

Fields

Input Help/Check

Currency/Quantity Fields

Indexes





 Srch Help

Built-In Type

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
<u>MAND</u>	☒	☒	<u>MANDT</u>	CLNT	3	0		0 Client
<u>MATNR</u>	☒	☒	<u>MATNR</u>	CHAR	40	0		0 Material Number
<u>WERKS</u>	☒	☒	<u>WERKS_D</u>	CHAR	4	0		0 Plant
<u>LGORT</u>	☒	☒	<u>LGORT_D</u>	CHAR	4	0		0 Storage location
<u>COUNTRY</u>	☐	☐	<u>/TROIC/COUNTRY</u>	CHAR	3	0		0 Country
<u>COUNTRY_GROUP</u>	☐	☐	<u>/TROIC/COUNTRY ...</u>	CHAR	4	0		0 Country Group
<u>MTART</u>	☐	☐	<u>MTART</u>	CHAR	4	0		0 Material type
<u>STOCKCHAR</u>	☐	☐	<u>/TROIC/STCKCHAR</u>	CHAR	18	0		0 Stock Charatcter
<u>STOCKCHARVALUE</u>	☐	☐	<u>/TROIC/STCKCHAR...</u>	CHAR	35	0		0 Stock Charatcter Value

Dictionary: Display View


Maintenance View [/TROIC/V_STKCHAR](#) Active

Short Description Character Value for Physical Stock

Attributes Table/Join Conditions **View Fields** Selection Conditions Maint.Status

View field	Data elem.	M...	DType	Length	Short description
MAND	MANDT	☐	CLNT	3	Client
MATNR	MATNR	☐	CHAR	40	Material Number
WERKS	WERKS_D	☐	CHAR	4	Plant
LGORT	LGORT_D	☐	CHAR	4	Storage location
COUNTRY	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
MTART	MTART	☐	CHAR	4	Material type
STOCKCHAR	/TROIC/STCKCHAR	☐	CHAR	18	Stock Charatcter
STOCKCHARVALUE	/TROIC/STCKCHARVALUE	☐	CHAR	35	Stock Charatcter Value
		☐			

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Display View "Character Value for Physical Stock": Overview



Character Value for Physical Stock

Material	Plnt	SLoc	Country	Cntry Grp	MTyp Stock Charactcter	+
*	2810	*	RO	*	RO10	0
*	2820	*	RO	*	RO20	0
27	2810	*	RO	*	HAWA RO01	BLUE_35
27	2820	*	RO	*	HAWA RO01	BLUE_35
28	2810	*	RO	*	HAWA RO01	YELLOW_124
28	2820	*	RO	*	HAWA RO01	YELLOW_124

SAFT Dataset - Tax Table, Movement Of Goods, Payments, Sales Invoices , Purchase Invoices, General Ledger Entries.

- /TROIC/SAFT_TAX: This table is used to map the SAP tax code to the corresponding SAFT tax code as defined by each country's local tax authority.
- View Name - /TROIC/V_SAFTTAX: Maintenance created on top of the custom table /TROIC/SAFT_TAX.
- T – code - /TROIC/SAFT_TAXCD.

Transparent Table /TROIC/SAFT_TAX Active

Short Description Master Data - SAFT Taxcode mapping table

 Attributes Delivery and Maintenance **Fields** Input Help/Check Currency/Quantity Fields Indexes

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
MANDT	☒	☒	MANDT	CLNT	3	0		0 Client
KALSM	☒	☒	KALSM_D	CHAR	6	0		0 Procedure (Pricing, Output Control, Acct. Det., Costing,...)
MWSKZ	☒	☒	MWSKZ	CHAR	2	0		0 Tax on sales/purchases code
SAFT_TAX_TYP	☒	☒	/TROIC/TAX_TYP	NUMC	3	0		0 SAFT Tax Type
SAFT_TAX_CODE	☒	☒	/TROIC/TAX_CODE	NUMC	6	0		0 SAFT Tax Code
COUNTRY	☐	☐	/TROIC/COUNTRY	CHAR	3	0		0 Country
COUNTRY_GROUP	☐	☐	/TROIC/COUNTRY_...	CHAR	4	0		0 Country Group
SAFT_TAXTYP_DESC	☐	☐	/TROIC/TAXTYP_D...	CHAR	225	0		0 SAFT tax type description
SAFT_TAXCOD_DESC	☐	☐	/TROIC/TAXCOD_D...	CHAR	255	0		0 SAFT Tax code description
TAX_PERCENTAGE	☐	☐	/TROIC/TAX_PERC...	DEC	9	2		0 SAFT Tax percentage
TAX_BASE_RATE	☐	☐	/TROIC/BASE_RATE	DEC	9	2		0 SAFT Tax Base Rate
LAND1	☐	☐	LAND1	CHAR	3	0		0 Country/Region Key
TAX_EXEMPT_CODE	☐	☐	/TROIC/TAX_EXEM...	CHAR	70	0		0 SAFT Tax Exempt Reason


Maintenance View [/TROIC/V_SAFTTAX](#) Active

Short Description View for /TROIC/SAFT_TAX

Attributes Table/Join Conditions **View Fields** Selection Conditions Maint.Status

View field	Table	Field	P Key	Data elem.	M...	DTyp	Length	Short description
MANDT	/TROIC/SAFT_TAX	MANDT	☒	MANDT	☐	CLNT	3	Client
KALSM	/TROIC/SAFT_TAX	KALSM	☒	KALSM_D	☐	CHAR	6	Procedure (Pricing, Output Cc
MWSKZ	/TROIC/SAFT_TAX	MWSKZ	☒	MWSKZ	☐	CHAR	2	Tax on sales/purchases code
SAFT_TAX_TYP	/TROIC/SAFT_TAX	SAFT_TAX_TYP	☒	/TROIC/TAX_TYP	☐	NUMC	3	SAFT Tax Type
SAFT_TAX_CODE	/TROIC/SAFT_TAX	SAFT_TAX_CODE	☒	/TROIC/TAX_CODE	☐	NUMC	6	SAFT Tax Code
COUNTRY	/TROIC/SAFT_TAX	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/SAFT_TAX	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
SAFT_TAXTYP_DESC	/TROIC/SAFT_TAX	SAFT_TAXTYP_DESC	☐	/TROIC/TAXTYP_DESC	☐	CHAR	225	SAFT tax type description
SAFT_TAXCOD_DESC	/TROIC/SAFT_TAX	SAFT_TAXCOD_DESC	☐	/TROIC/TAXCOD_DESC	☐	CHAR	255	SAFT Tax code description
TAX_PERCENTAGE	/TROIC/SAFT_TAX	TAX_PERCENTAGE	☐	/TROIC/TAX_PERCENTAGE	☐	DEC	9	SAFT Tax percentage
TAX_BASE_RATE	/TROIC/SAFT_TAX	TAX_BASE_RATE	☐	/TROIC/BASE_RATE	☐	DEC	9	SAFT Tax Base Rate
LAND1	/TROIC/SAFT_TAX	LAND1	☐	LAND1	☐	CHAR	3	Country/Region Key
TAX_EXEMPT_CODE	/TROIC/SAFT_TAX	TAX_EXEMPT_CODE	☐	/TROIC/TAX_EXEMPT_CD	☐	CHAR	70	SAFT Tax Emempt Reason
			☐		☐			
			☐		☐			
			☐		☐			
			☐		☐			

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "View for /TROIC/SAFT_TAX": Overview

 **New Entries**     

View for /TROIC/SAFT_TAX

Proc.	Tx Tax Type	SAFT Taxcd	Country	Cntry Grp	Tax Type Description
OTXRO	A0 300	310304	RO	*	LIST OF VAT CODES FOR SALES TRANSACTIONS
OTXRO	A1 300	310309	RO	*	LIST OF VAT CODES FOR SALES TRANSACTIONS
OTXRO	A2 300	310310	RO	*	LIST OF VAT CODES FOR SALES TRANSACTIONS
OTXRO	A3 300	310311	RO	*	LIST OF VAT CODES FOR SALES TRANSACTIONS
OTXRO	RO 309	310312	RO	*	LIST OF VAT CODES FOR SALES TRANSACTIONS
OTXRO	V0 300	328302	RO	*	LIST OF VAT CODES FOR SALES TRANSACTIONS
OTXRO	V1 300	309101	RO	*	LIST OF VAT CODES FOR PURCHASES WITH 100% DEDUCTIBLE VAT
OTXRO	V2 300	320102	RO	*	LIST OF VAT CODES FOR PURCHASES WITH 50% DEDUCTIBLE VAT SUBJECT TO PRO RATA ALLOCATION
OTXRO	V3 300	330103	RO	*	LIST OF VAT CODES FOR PURCHASES WITH 50% VAT WHERE DEDUCTIBILITY UNDER THE PRO RATA METHOD IS UNKNOWN

SAFT Dataset – Assets Transactions

- Table Name: /TROIC/D_ASTTYP – The Table is created to map the analysis types to each company code.
- View Name - /TROIC/V_ASTTYPE: This Table holds the Asset Transaction Type and SAFT Asset traction type (like which type of Asset Transaction is it handling).
- T-code - /TROIC/SAFT_ASTTYP.

Transparent Table **/TROIC/D_ASTTYP** Active

Short Description **Asset Transaction Type - SAFT Type Mapping**

Attributes | Delivery and Maintenance | **Fields** | Input Help/Check | Currency/Quantity Fields | Indexes


   **Srch Help** **Built-In Type**

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
MANDT	☒	☒	MANDT	CLNT	3	0		0 Client
ANBWA	☒	☒	ANBWA	CHAR	3	0		0 Asset Transaction Type
COUNTRY	☐	☐	/TROIC/COUNTRY	CHAR	3	0		0 Country
COUNTRY_GROUP	☐	☐	/TROIC/COUNTRY ...	CHAR	4	0		0 Country Group
SAFT_ATR_TYP	☐	☒	/TROIC/SAFT_ATR...	CHAR	3	0		0 SAFT Asset traction type

Maintenance View	/TROIC/V_ASTTYPE	Active
Short Description	Maintenance View for Asset Transaction Types	
Attributes	Table/Join Conditions	View Fields
Selection Conditions	Maint.Status	

View field	Table	Field	P Key	Data elem.	M...	DType	Length	Short description
MANDT	/TROIC/D_ASTTYP	NDT	☒	MANDT	☐	CLNT	3	Client
ANBWA	/TROIC/D_ASTTYP	ANBWA	☒	ANBWA	☐	CHAR	3	Asset Transaction Type
COUNTRY	/TROIC/D_ASTTYP	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/D_ASTTYP	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
SAFT_ATR_TYP	/TROIC/D_ASTTYP	SAFT_ATR_TYP	☐	/TROIC/SAFT_ATR_TYP	☐	CHAR	3	SAFT Asset traction type

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "Maintenance View for Asset Transaction Types": Overview			
New Entries			
Maintenance View for Asset Transaction Types			
A.TrnsType	Country	Cntry Grp	SAFT TYP
100	RO	*	Other transactions
500	RO	*	Depreciation

SAFT Dataset – Assets

- Table Name - /TROIC/D_CTLOG: This Table holds the Company, Asset Definition Key, Definition Key Sequential Number, Definition Key Offset, Definition Key Length and Definition Key Content.

- View Name: /TROIC/V_CTLOG - Maintenance created on top of the custom table /TROIC/D_CTLOG.
- T-code - /TROIC/SAFT_CTLOG.

Transparent Table

/TROIC/D_CTLOG

Active

Short Description

SAF - T Catalog

Attributes

Delivery and Maintenance

Fields

Input Help/Check

Currency/Quantity Fields

Indexes

✕

📄

🔍

📁

📋

↶

↷

↺

↻

🔍

Srch Help

Built-In Type

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
MANDT	☒	☒	MANDT	CLNT	3	0		0 Client
BUKRS	☒	☒	BUKRS	CHAR	4	0		0 Company Code
AST_DEF_KEY	☒	☒	/TROIC/SAFT_AST...	CHAR	10	0		0 Asset Definition Key
COUNTRY	☐	☐	/TROIC/COUNTRY	CHAR	3	0		0 Country
COUNTRY_GROUP	☐	☐	/TROIC/COUNTRY ...	CHAR	4	0		0 Country Group
DEF_KEY_SEQ_NMBR	☐	☐	/TROIC/SAFT_SEQ...	NUMC	3	0		0 Definition Key Sequential Number
DEF_KEY_OFFSET	☐	☐	/TROIC/SAFT_DEF...	CHAR	255	0		0 Definition Key Offset
DEF_KEY_LENGTH	☐	☐	/TROIC/SAFT_DEF...	CHAR	255	0		0 Definition Key Length
DEF_KEY_CONTENT	☐	☐	/TROIC/SAFT_DEF...	CHAR	25	0		0 Definition Key Content

Maintenance View

/TROIC/V_CTLOG

Active

Short Description

Maintenance for /TROIC/D_CTLOG

Attributes

Table/Join Conditions

View Fields

Selection Conditions

Maint.Status

✕

📄

🔍

📁


📋

🔍

Table fields

View field	Table	Field	P Key	Data elem.	M...	DType	Length	Short description
MANDT	/TROIC/D_CTLOG	MANDT	☒	MANDT	☐	CLNT	3	Client
BUKRS	/TROIC/D_CTLOG	BUKRS	☒	BUKRS	☐	CHAR	4	Company Code
AST_DEF_KEY	/TROIC/D_CTLOG	AST_DEF_KEY	☒	/TROIC/SAFT_ASTDEF_KEY	☐	CHAR	10	Asset Definition Key
COUNTRY	/TROIC/D_CTLOG	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/D_CTLOG	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
DEF_KEY_SEQ_NMBR	/TROIC/D_CTLOG	DEF_KEY_SEQ_NMBR	☐	/TROIC/SAFT_SEQ_NMBR	☐	NUMC	3	Definition Key Sequential Number
DEF_KEY_OFFSET	/TROIC/D_CTLOG	DEF_KEY_OFFSET	☐	/TROIC/SAFT_DEF_KEY_OFFSET	☐	CHAR	255	Definition Key Offset
DEF_KEY_LENGTH	/TROIC/D_CTLOG	DEF_KEY_LENGTH	☐	/TROIC/SAFT_DEF_KEY_LENGTH	☐	CHAR	255	Definition Key Length
DEF_KEY_CONTENT	/TROIC/D_CTLOG	DEF_KEY_CONTENT	☐	/TROIC/SAFT_DEF_KEY_CONTENT	☐	CHAR	25	Definition Key Content
			☐		☐			
			☐		☐			
			☐		☐			

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "Maintenance for /TROIC/D_CTLOG": Overview

New Entries      

Maintenance for /TROIC/D_CTLOG

CoCd	Asset key	Country	Cntry Grp	Dfseqnum	Definition Key Offset
2810	No Asset Definition Key	RO	*	Group1AssetEvaluationKey	✓
2810	Investment Support Asset	RO	*	Group2AssetEvaluationKey	✓
2820	No Asset Definition Key	RO	*	Group1AssetEvaluationKey	✓
2820	Investment Support Asset	RO	*	Group2AssetEvaluationKey	✓

SAFT Dataset – UOM

- Table Name - /TROIC/D_UOMMAP: This Table holds the Base Unit of Measure, Country, SAF-T Unit of Measure and SAF-T Description.
- View - /TROIC/V_UOMMAP - Maintenance created on top of the custom table /TROIC/D_UOMMAP.
- T-code - /TROIC/SAFT_UOM.

Transparent Table								
Short Description								
Attributes								
Delivery and Maintenance								
Fields								
Input Help/Check								
Currency/Quantity Fields								
Indexes								
          Srch Help Built-In Type								
Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
<u>MANDT</u>	☒	☒	<u>MANDT</u>	CLNT	3	0		0 Client
<u>MEINS</u>	☒	☒	<u>MEINS</u>	UNIT	3	0		0 Base Unit of Measure
<u>COUNTRY</u>	☐	☐	<u>/TROIC/COUNTRY</u>	CHAR	3	0		0 Country
<u>COUNTRY_GROUP</u>	☐	☐	<u>/TROIC/COUNTRY_...</u>	CHAR	4	0		0 Country Group
<u>SAFT_UOM</u>	☐	☐	<u>/TROIC/SAFT_UOM</u>	CHAR	4	0		0 SAF-T Unit of Measure
<u>SAFT_DESCRIPTION</u>	☐	☐	<u>/TROIC/SAFT_DES</u>	CHAR	255	0		0 SAF-T Description

Dictionary: Display View


Maintenance View: /TROIC/V_UOMMAP Active

Short Description: Maintain Unit of Measures

Attributes | Table/Join Conditions | **View Fields** | Selection Conditions | Maint.Status

View field	Table	Field	P Key	Data elem.	M...	DType	Length	Short description
MANDT	/TROIC/D_UOMMAP	MANDT	☒	MANDT	☐	CLNT	3	Client
MEINS	/TROIC/D_UOMMAP	MEINS	☒	MEINS	☐	UNIT	3	Base Unit of Measure
COUNTRY	/TROIC/D_UOMMAP	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/D_UOMMAP	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
SAFT_UOM	/TROIC/D_UOMMAP	SAFT_UOM	☐	/TROIC/SAFT_UOM	☐	CHAR	4	SAF-T Unit of Measure
SAFT_DESCRIPTION	/TROIC/D_UOMMAP	SAFT_DESCRIPTION	☐	/TROIC/SAFT_DES	☐	CHAR	255	SAF-T Description

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "Maintain Unit of Measures": Overview


New Entries







Maintain Unit of Measures

	BUn	Country	Cntry Grp	RO UoM	Description
	BT	RO	*	XBQ	BOTTLE, PROTECTED CYLINDRICAL
	CCM	RO	*	CMQ	CUBIC CENTIMETRE
	CM	RO	*	CMT	CENTIMETRE
	EA	RO	*	EA	EACH
	G	RO	*	GRM	GRAM
	KG	RO	*	28	KILOGRAM PER SQUARE METRE
	KGM	RO	*	KGM	KILOGRAM
	L	RO	*	LTR	LITRE
	M	RO	*	MTR	METRE
	M2	RO	*	MTK	SQUARE METRE
	M3	RO	*	MTQ	CUBIC METRE
	MG	RO	*	MGM	MILLIGRAM

SAFT Dataset – Payment Methods

- Table Name - /TROIC/D_PAYMCH : This Table holds the Company Code, Payment Method, Payment Mechanism, Payment mechanism Description, SAF-T Payment Method and SAF-T Payment method Description.
- View Name - Maintenance created on top of the custom table /TROIC/V_PAYMCH.
- T-code - /TROIC/SAFT_PAYM

Transparent Table

/TROIC/D_PAYMCH

Active

Short Description

SAFT : Payment Method Mappings

Attributes

Delivery and Maintenance

Fields


Input Help/Check

Currency/Quantity Fields

Indexes







Srch Help

Built-In Type

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
MANDT	☒	☒	MANDT	CLNT	3	0		0 Client
BUKRS	☒	☒	BUKRS	CHAR	4	0		0 Company Code
ZLSCH	☒	☒	SCHZW_BSEG	CHAR	1	0		0 Payment Method
COUNTRY	☐	☐	/TROIC/COUNTRY	CHAR	3	0		0 Country
COUNTRY_GROUP	☐	☐	/TROIC/COUNTRY ...	CHAR	4	0		0 Country Group
PAYM_MECH	☐	☐	/TROIC/SAFT PAY...	CHAR	3	0		0 Payment Mechaism
PAYM_MECH_DES	☐	☐	/TROIC/SAFT PAY...	CHAR	255	0		0 Payment Mechanism Description
PAYM_METHOD	☐	☐	/TROIC/SAFT PAY...	CHAR	3	0		0 SAF-T Payment Method
PAYM_METHOD_DES	☐	☐	/TROIC/SAFT PAY...	CHAR	255	0		0 SAF-T Payment Method Description

Maintenance View

/TROIC/V_PAYMCH

Active

Short Description

Maintenance for /TROIC/D_PAYMCH

Attributes

Table/Join Conditions

View Fields

Selection Conditions

Maint.Status

Table fields

View field	Table	Field	P Key	Data elem.	M...	DTyp	Length	Short description
MANDT	/TROIC/D_PAYMCH	MANDT	☒	MANDT	☐	CLNT		3 Client
BUKRS	/TROIC/D_PAYMCH	BUKRS	☒	BUKRS	☐	CHAR		4 Company Code
ZLSCH	/TROIC/D_PAYMCH	ZLSCH	☒	SCHZW_BSEG	☐	CHAR		1 Payment Method
COUNTRY	/TROIC/D_PAYMCH	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR		3 Country
COUNTRY_GROUP	/TROIC/D_PAYMCH	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR		4 Country Group
PAYM_MECH	/TROIC/D_PAYMCH	PAYM_MECH	☐	/TROIC/SAFT_PAYMECH	☐	CHAR		3 Payment Mechanism
PAYM_MECH_DES	/TROIC/D_PAYMCH	PAYM_MECH_DES	☐	/TROIC/SAFT_PAYDES	☐	CHAR	255	Payment Mechanism Description
PAYM_METHOD	/TROIC/D_PAYMCH	PAYM_METHOD	☐	/TROIC/SAFT_PAYMETHOD	☐	CHAR	3	SAF-T Payment Method
PAYM_METHOD_DES	/TROIC/D_PAYMCH	PAYM_METHOD_D...	☐	/TROIC/SAFT_PAYMETHOD_DES	☐	CHAR	255	SAF-T Payment Method Description
			☐		☐			

For Accessing these table use the below path, and user can directly add entries to the table.

- **Favorites**
- ▼ **User Menu for ABHISHAD**
 - ▼ **ONESOURCE Indirect Tax Compliance**
 - > **OIC Report and Logs**
 - ▼ **OIC Config**
 - ▼ **SAF-T Configurations**
 - **SAFT Country Group Mapping**
 - **SAFT Country Group Assignment Mapping**
 - **SAFT Payment Method Mapping**
 - **SAFT Movement Type**
 - **SAFT UoM Mapping**

By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "Maintenance for /TROIC/D_PAYMCH": Overview

New Entries

Maintenance for /TROIC/D_PAYMCH

	CoCd	P..	Country	Cntry Grp	Pay Mech	Payment Mechanism Description
	2810	E	RO	*	42	FOR PAYMENT BY BANK TRANSFER
	2810	I	RO	*	41	FOR PAYMENT BY BANK TRANSFER
	2810	N	RO	*	10	FOR PAYMENT BY CASH
	2820	E	RO	*	42	FOR PAYMENT BY BANK TRANSFER
	2820	I	RO	*	41	FOR PAYMENT BY BANK TRANSFER

SAFT Dataset – Movement types

- Table Name - /TROIC/D_MVTYP: This Table holds the Company Code, Valuation Grouping Code, Valuation Class, Movement Type (Inventory Management), Plant, Document Type, Debit/Credit Indicator, G/L Account, Account Number, ANAF Movement Type and SAF-T Movement Type Description.
- View Name - /TROIC/V_MVTYP - Maintenance created on top of the custom table /TROIC/D_MVTYP.
- T- code - /TROIC/SAFT_MVTYP.

Transparent Table

/TROIC/D_MVTYPE

Active

Short Description

SAF-T RO - SAP Movement Types to ANAF Movement types

Attributes

Delivery and Maintenance

Fields

Input Help/Check

Currency/Quantity Fields

Indexes

Srch Help

Built-In Type


1 / 14

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
<u>MANDT</u>	☒	☒	<u>MANDT</u>	CLNT	3	0		0 Client
<u>BUKRS</u>	☒	☒	<u>BUKRS</u>	CHAR	4	0		0 Company Code
<u>BWMO</u>	☒	☒	<u>BWMO</u>	CHAR	4	0		0 Valuation Grouping Code
<u>BKLAS</u>	☒	☒	<u>BKLAS</u>	CHAR	4	0		0 Valuation Class
<u>EWART</u>	☒	☒	<u>EWART</u>	CHAR	3	0		0 Movement type (inventory management)
<u>WERKS</u>	☒	☒	<u>WERKS_D</u>	CHAR	4	0		0 Plant
<u>BLART</u>	☒	☒	<u>BLART</u>	CHAR	2	0		0 Document Type
<u>SHKZG</u>	☒	☒	<u>SHKZG</u>	CHAR	1	0		0 Debit/Credit Indicator
<u>HKONT</u>	☒	☒	<u>HKONT</u>	CHAR	10	0		0 General Ledger Account
<u>COUNTRY</u>	☐	☐	<u>/TROIC/COUNTRY</u>	CHAR	3	0		0 Country
<u>COUNTRY_GROUP</u>	☐	☐	<u>/TROIC/COUNTRY ...</u>	CHAR	4	0		0 Country Group
<u>LOKKT</u>	☐	☐	<u>LOKKT</u>	CHAR	10	0		0 Account Number in the Local Chart of Accounts
<u>SAFT_MOV_TYP</u>	☐	☐	<u>/TROIC/SAFT_MVT...</u>	CHAR	3	0		0 ANAF Movement Type
<u>SAFT_MOV_DES</u>	☐	☐	<u>/TROIC/SAFT_MOV...</u>	CHAR	255	0		0 SAF-T Movement Type Description

Maintenance View	/TROIC/V_MVTYP	Active
Short Description	Maintain ANAF Movement types	
Attributes	Table/Join Conditions	View Fields
Selection Conditions		
Maint.Status		

View field	Table	Field	P Key	Data elem.	M...	DType	Length	Short description
MANDT	/TROIC/D_MVTYP	MANDT	☒	MANDT	☐	CLNT	3	Client
BUKRS	/TROIC/D_MVTYP	BUKRS	☒	BUKRS	☐	CHAR	4	Company Code
BWMOD	/TROIC/D_MVTYP	BWMOD	☒	BWMOD	☐	CHAR	4	Valuation Grouping Code
BKLAS	/TROIC/D_MVTYP	BKLAS	☒	BKLAS	☐	CHAR	4	Valuation Class
BWART	/TROIC/D_MVTYP	BWART	☒	BWART	☐	CHAR	3	Movement type (inventory management)
WERKS	/TROIC/D_MVTYP	WERKS	☒	WERKS_D	☐	CHAR	4	Plant
BLART	/TROIC/D_MVTYP	BLART	☒	BLART	☐	CHAR	2	Document Type
SHKZG	/TROIC/D_MVTYP	SHKZG	☒	SHKZG	☐	CHAR	1	Debit/Credit Indicator
HKONT	/TROIC/D_MVTYP	HKONT	☒	HKONT	☐	CHAR	10	General Ledger Account
COUNTRY	/TROIC/D_MVTYP	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/D_MVTYP	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
LOKKT	/TROIC/D_MVTYP	LOKKT	☐	LOKKT	☐	CHAR	10	Account Number in the Local Chart of Accounts
SAFT_MOV_TYP	/TROIC/D_MVTYP	SAFT_MOV_TYP	☐	/TROIC/SAFT_MVTYP	☐	CHAR	3	ANAF Movement Type
SAFT_MOV_DES	/TROIC/D_MVTYP	SAFT_MOV_DES	☐	/TROIC/SAFT_MOVDES	☐	CHAR	255	SAF-T Movement Type Description
			☐		☐			
			☐		☐			

For Accessing these table use the below path, and user can directly add entries to the table.



By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "Maintain ANAF Movement types": Overview

New Entries

CoCd	VGCd	ValCd	M...	Plnt	Type	D/C	G/L Account	Country	Cntry Grp	Local Acct No.	MVT TYP	Description
2810	0001	3100	101	2810		✓		RO	*		10	PURCHASE
2810	0001	3100	102	2810		✓		RO	*		50	RETURN OF PURCHASE
2810	0001	3100	561	2810		✓		RO	*		20	PRODUCTION
2810	0001	3100	601	2810		✓		RO	*		30	SALE OF STOCK
2810	0001	3100	602	2810		✓		RO	*		40	RETURN OF SALES
2820	0001	3100	101	2820		✓		RO	*		10	PURCHASE
2820	0001	3100	102	2820		✓		RO	*		50	RETURN OF PURCHASE
2820	0001	3100	561	2820		✓		RO	*		20	PRODUCTION
2820	0001	3100	601	2820		✓		RO	*		30	SALE OF STOCK
2820	0001	3100	602	2820		✓		RO	*		40	RETURN OF SALES

SAFT Dataset – Asset Transaction Rules Config Table

- /TROIC/D_ATRCFG: This table is used to maintain the transaction rules configuration for assets, mapping transaction type group, subledger-specific line item type, and transaction type category.
- View Name – /TROIC/V_ATR_CFG– Maintenance view created on top of the custom table /TROIC/D_ATRCFG.
- T-code – /TROIC/SAFT_ATRCFG.

Dictionary: Display Table

Transparent Table /TROIC/D_ATRCFG Active

Short Description Custom table for asset transaction rules.

Attributes Delivery and Maintenance **Fields** Input Help/Check Currency/Quantity Fields Indexes

Field	Key	Init...	Data element	Data Type	Length	Deci...	Coordinate	Short Description
MANDT	☒	☒	MANDT	CLNT	3	0		0 Client
FIELDNAME	☒	☒	/TROIC/SAFT_RUL...	CHAR	20	0		0 data element for rule type
BWAGRP	☒	☒	BWAGRP	CHAR	2	0		0 Transaction Type Group
SLALITTYPE	☒	☒	SLALITTYPE	NUMC	5	0		0 Subledger-Specific Line Item Type
MOVCAT	☒	☒	FAA_MOVCAT	CHAR	2	0		0 Transaction Type Category
COUNTRY	☐	☐	/TROIC/COUNTRY	CHAR	3	0		0 Country
COUNTRY_GROUP	☐	☐	/TROIC/COUNTRY_...	CHAR	4	0		0 Country Group
AMOUNT_SIGNAGE	☐	☐	/TROIC/SAFT_AMT...	CHAR	30	0		0 Data element Amount Sign
ACTIVE	☐	☐	/TROIC/ACTIVE	CHAR	1	0		0 OIC Is Active flag

Maintenance View /TROIC/V_ATR_CFG Active

Short Description SAFT Asset Transactions - Amount fields configuration

Attributes Table/Join Conditions **View Fields** Selection Conditions Maint.Status


View field	Table	Field	P Key	Data elem.	M...	DType	Length	Short description
MANDT	/TROIC/D_ATRCFG	MANDT	☒	MANDT	☐	CLNT	3	Client
FIELDNAME	/TROIC/D_ATRCFG	FIELDNAME	☒	/TROIC/SAFT RULETYPE	☐	CHAR	20	data element for rule type
BWAGRP	/TROIC/D_ATRCFG	BWAGRP	☒	BWAGRP	☐	CHAR	2	Transaction Type Group
SLALITTYPE	/TROIC/D_ATRCFG	SLALITTYPE	☒	SLALITTYPE	☐	NUMC	5	Subledger-Specific Line Item
MOVCAT	/TROIC/D_ATRCFG	MOVCAT	☒	FAA_MOVCAT	☐	CHAR	2	Transaction Type Category
COUNTRY	/TROIC/D_ATRCFG	COUNTRY	☐	/TROIC/COUNTRY	☐	CHAR	3	Country
COUNTRY_GROUP	/TROIC/D_ATRCFG	COUNTRY_GROUP	☐	/TROIC/COUNTRY_GROUP	☐	CHAR	4	Country Group
AMOUNT_SIGNAGE	/TROIC/D_ATRCFG	AMOUNT_SIGNAGE	☐	/TROIC/SAFT AMTSIGN	☐	CHAR	30	Data element Amount Sign
ACTIVE	/TROIC/D_ATRCFG	ACTIVE	☐	/TROIC/ACTIVE	☐	CHAR	1	OIC Is Active flag

For Accessing these table use the below path, and user can directly add entries to the table.

- User Menu for ABHISHAD
 - ONESOURCE Indirect Tax Compliance
 - OIC Report and Logs
 - OIC Config
 - SAFT-T Configurations
 - SAFT Country Group Mapping
 - SAFT Country Group Assignment Mapping
 - SAFT Payment Method Mapping
 - SAFT Movement Type
 - SAFT UoM Mapping
 - SAFT Catalog
 - SAFT Invoice Document Type
 - SAFT Asset Trns. Type mapping
 - SAFT Asset Trns. Amt Fld config
 - GL SAF-T Account Type
 - Taxcode Mapping
 - Analysis Type

By Clicking on the NEW ENTRIES, the user can add entries to the table

Change View "SAFT Asset Transactions - Amount fields configuration": Ov

Amount Field Name	T...	SLALiTy	Trans.Type Cat.	Country	Cntry Grp	Amount Signage	Active
Acquisition ...	10	07010		RO	*	VALUE	☒
Acquisition ...	10	07040		RO	*	POSITIVE	☒
Book value o...	10	07040		RO	*	POSITIVE	☒
Book value o...	10	07205		RO	*	VALUE	☒
Book value o...	20	07010		RO	*	POSITIVE	☒
Book value o...	25	07020		RO	*	POSITIVE	☒
Book value o...	30	07010		RO	*	POSITIVE	☒
Book value o...	55	07205		RO	*	POSITIVE	☒
Book value o...	70	07030		RO	*	VALUE	☒
Book value o...	80	07210		RO	*	POSITIVE	☒
Asset transa...	10	07010		RO	*	POSITIVE	☒
Asset transa...	20	00000	12	RO	*	VALUE	☒
Asset transa...	25	07010		RO	*	NEGATIVE	☒
Asset transa...	30	07010		RO	*	POSITIVE	☒
Asset transa...	30	07020		RO	*	POSITIVE	☒
Asset transa...	40	07010		RO	*	POSITIVE	☒
Asset transa...	55	07205		RO	*	VALUE	☒

Enhancement Spots – Badls

Two BADls are available to accommodate adjustments tailored to customer requirements. The first occurs before finalizing the output line, while the second takes place after the field mapping. These BADls are presented as enhancement spots, allowing customers to implement changes as needed.

1. /TROIC/ENH_OIC_MOD_LINE:

This BADl offers a dynamic enhancement spot during the creation of the output table line, providing flexibility through its importing and changing parameters. Customers can customize it to align with their specific requirements.


2. /TROIC/ENH_OIC_MOD_AFTER_MAP:

This BADl presents a dynamic enhancement spot after the creation of the output table, triggered post-field mapping and before sending the data to OIC. Customers can tailor it to their needs by leveraging the importing and changing parameters.

USER GUIDE

Users are presented with a selection screen within this integration, allowing them to filter the necessary data that needs to be transmitted to OIC.

This selection screen can be accessed through the integration user menu or the tcode:
`/TROIC/DATA_RPRT_OIC`



After configuring all the necessary settings, users can execute this program by entering mandatory fields in the selection screen after choosing the 'Report' option. Within this menu, users have the flexibility to either download the data exclusively or send data to OIC without downloading. Both options can be utilized independently or in combination as needed.

NOTE As of this release, VAT & ESL, G/L transactions, INTRASTAT and SAF-T reports are tested end-to-end with standard field mappings.

OIC Data Transfer

Execution Type

☒ Report

☐ Import status

Report Type

☒ VAT and ESL

☐ GL Transactions

☐ Intrastat

☐ SAF-T

Selection Parameters

Company Code	☒	to	☒	
Document Type	☒	to	☒	
Fiscal Year	☒	to	☒	
Posting Date	☒	to	☒	
Document Number		to		
Document Status		to		
Reference		to		
Reference procedure		to		
Reference Key		to		
Entry Date		to		

Download

☒ Download

☒ Application Server

Server Path

Server File Name

☐ Presentation Server

Local Path

Local File Name

☐ Send data to OIC

Select the report type as per requirement. Selection parameters may change based on the report type selected. Once all the required data has been entered, the program can be run either in Foreground or Background.

Download

Users have two options to download the data or send the data to OIC.


For downloading, follow below steps.

- Application Server- Choose this option to save the file in the directory (AL11 Transaction code) while executing in the background or foreground.
- Presentation Server- Choose this option to download the file to your local folder while executing in the foreground only.

NOTE: Specify the file name extension with .csv.

Send data to OIC

For sending the data to OIC, the specification details are required. User can maintain these details in 'OIC Import Specification' configuration table by clicking '/TROIC/IMPSPEC - OIC SPEC Mapping'



Select this option to Send the data to OIC.

The screenshot shows a dialog box titled 'Download or Send to OIC'. It has two radio buttons: 'Download' (unchecked) and 'Send data to OIC' (checked and highlighted with a red rectangle). Below the radio buttons, there are five input fields: 'Import name' (Test SAP_OIC1), 'Import specification name' (SAP-OIC_Import Spec), 'Specification name' (SAP_OIC11), 'Import type name' (Transactions), and 'OIC File Name' (checked).

Based on the OIC Import Specification config table, the specification details are fetched automatically when user clicks 'Send data to OIC'.

Below are the example screenshots.

When report type is selected as 'VAT-ESL'

The screenshot shows a dialog box titled 'Download or Send to OIC'. It has two radio buttons: 'Download' (checked) and 'Application Server' (selected). Below the radio buttons, there are two sections: 'Server Path' and 'Presentation Server'. The 'Send data to OIC' checkbox is checked. Below it, there are four input fields: 'Import name' (SAP Integration Test 01), 'Import specification name' (Auto_Upload Test Spec), 'Specification name' (Auto_5C upload), and 'Import type name' (Transactions). The 'Import specification name' and 'Specification name' fields are highlighted with a red rectangle.

When report type is selected as 'INTRASTAT'

Download or Send to OIC	
☒ Download	
☒ Application Server	
Server Path	D:\usr\sap\FS4\D00\data
Server File Name	TES17_OIC_INTRASTAT.CSV
☐ Presentation Server	
Local Path	
Local File Name	
☒ Send data to OIC	
Import name	Intrastat source file
Import specification name	Alloc_Intrastat
Specification name	Alloc_Intrastat
Import type name	Intrastat

When report type is selected as 'G/L Transactions'

Download or Send to OIC	
☒ Download	
☒ Application Server	
Server Path	
Server File Name	
☐ Presentation Server	
Local Path	
Local File Name	
☒ Send data to OIC	
Import name	VN_GLImport_Test_01
Import specification name	Alloc_GLTransactions
Specification name	Alloc_GLTransactions
Import type name	GeneralLedger

When Report type is selected as 'SAF-T' and Dataset which we want to send to OIC Should be selected.

Send data to OIC

For sending the data to OIC, the specification details are required. User can maintain these details in 'OIC Import Specification' configuration table by clicking '/TROIC/IMPSPEC – OIC SPEC Mapping'

Display View "OIC Import Specification": Overview						
OIC Import Specification						
Report Type	Country	Sort Order	Active	Import Name	Import Specification	Specification Name
SAFT-ASSET TRJ	RO	000010	☒	SAFT_ASSET_TRANSACTIONS	AssetTransactions_Connector	DTR2
SAFT-ANALYSI...	RO	000010	☒	SAFT_ANALYSIS_TYPE	AnalysisType_Connector	DTR2
SAFT-CUSTOME...	RO	000010	☒	SAFT_CUSTOMERS	Customers_Connector	DTR2
SAFT-GL ACCO...	RO	000010	☒	SAFT_GL_ACCOUNTS	GLAccounts_Connector	DTR2
SAFT-GENERAL...	RO	000010	☒	SAFT_GLE	GLEntries_Connector	DTR2
SAFT-MOVEMEN...	RO	000010	☒	SAFT_MOVEMENT_TYPE	MovementTypeTable_Connector	DTR2
SAFT-MOVEMEN...	RO	000010	☒	SAFT_MOVEMENT_OF_GOODS	MovementOfGoods_Connector	DTR2
SAFT-OWNERS	RO	000010	☒	SAFT_OWNERS	Owners_Connector	DTR2
SAFT-PAYMENTS	RO	000010	☒	SAFT_PAYMENTS	Payments_Connector	DTR2
SAFT-PURCHAS...	RO	000010	☒	SAFT_PURCHASE_INVOICES	PurchaseInvoices_Connector	DTR2
SAFT-PRODUCTS	RO	000010	☒	SAFT_PRODUCTS	Product_Connector	DTR2
SAFT-PHYSICA...	RO	000010	☒	SAFT_PHYSICAL_STOCK	PhysicalStock_Connector	DTR2
SAFT-SALES I...	RO	000010	☒	SAFT_SALES_INVOICES	SalesInvoices_Connector	DTR2
SAFT-SUPPLIE...	RO	000010	☒	SAFT_SUPPLIERS	Suppliers_Connector	DTR2
SAFT-TAX	RO	000010	☒	SAFT_TAX_TABLE	TaxTable_Connector	DTR2
SAFT-UOM	RO	000010	☒	SAFT_UOM_TABLE	UOM_Connector	DTR2
VAT ESL		000001	☒	SAP Integration Test 01	Auto_Upload Test Spec	Auto_5C upload

Download

Users have two options to download the data.

For downloading, follow below steps.

1. Application Server- Choose this option to save the files of all the selected datasets in the directory (AL11 Transaction code) while executing in the background or foreground.
2. Presentation Server- Choose this option to download the files of all the selected datasets to your local folder while executing in the foreground only.

OIC Data Transfer

Report Type

☐ VAT and ESL
☐ GL Transactions
☐ Intrastat
☒ SAF-T

Country

RO

OIC Data Transfer

☐ Send data to OIC

Selection Parameters

Company Code

2310

to

2820

Fiscal Year

2026

Posting period

1

to

3

Dataset Selection

GLA

Customer

Supplier

Assets

UOMTable

TaxTable

AnalysisTyp

☒ GL Accounts

Ledger

OL

G/L Account

to

Download

☒ Download
☒ Application Server

Server Path

\\GN4 FINAL SUM\\SUM\\abap\\doc

☐ Presentation Server

Local Path

NOTE: For SAF-T report, directly specify the path.

OIC Data Transfer

Execution Type
☒ Report
☐ Import status

Report Type
☐ VAT and ESL
☐ GL Transactions
☐ Intrastat
☒ SAF-T
Country

OIC Data Transfer
☒ Send data to OIC

Selection Parameters
Company Code ☒ to ☒
Fiscal Year ☒ to ☒
Posting period ☒ to ☒

Dataset Selection
☒ GLA ☐ Customer ☐ Supplier ☐ Assets ☐ UOMTable ☐ TaxTable ☐ AnalysisTyp
☒ GL Accounts
Ledger ☒
G/L Account to

Import Specification Parameters
Import Name
Import Specification Name
Specification Name
Import Type Name

Once executed per the above selection screen, the file will be downloaded to the specified File Path, data is sent to OIC and the status of each call will be displayed at the end with a unique 'import id'.

Based on OIC import specification configuration table, the specification details are fetched automatically when user clicks 'Send data to OIC'.

Log Report												
Log Counter	Import ID	Co.C.	P.	Fisc.	Report Type	Date	Time	User Name	Program name	Call Type	Import Status	OIC Communication Status
2454	571	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:07:31	PAVANK	/TROIC/DATA_RPRT_OIC	DELETE	DELETE	200-Successful
2455	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:42	PAVANK	/TROIC/DATA_RPRT_OIC	Placeholder		202-Successful
2456	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:46	PAVANK	/TROIC/DATA_RPRT_OIC	Upload		200-Successful
2457	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:55	PAVANK	/TROIC/DATA_RPRT_OIC	Inoast		200-Successful
2458	727	2810	11	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:58	PAVANK	/TROIC/DATA_RPRT_OIC	Placeholder		202-Successful
2459	727	2810	11	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:03	PAVANK	/TROIC/DATA_RPRT_OIC	Upload		200-Successful
2460	727	2810	11	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:09	PAVANK	/TROIC/DATA_RPRT_OIC	Inoast		200-Successful
2461	563	2810	12	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:10	PAVANK	/TROIC/DATA_RPRT_OIC	DELETE	DELETE	200-Successful
2462	728	2810	12	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:11	PAVANK	/TROIC/DATA_RPRT_OIC	Placeholder		202-Successful
2463	728	2810	12	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:13	PAVANK	/TROIC/DATA_RPRT_OIC	Upload		200-Successful
2464	728	2810	12	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:19	PAVANK	/TROIC/DATA_RPRT_OIC	Inoast		200-Successful
2465	729	2810	10	2025	SAFT-CUSTOMERS	10.03.2026	07:10:20	PAVANK	/TROIC/DATA_RPRT_OIC	Placeholder		202-Successful
2466	729	2810	10	2025	SAFT-CUSTOMERS	10.03.2026	07:11:20	PAVANK	/TROIC/DATA_RPRT_OIC	Upload		200-Successful
2467	729	2810	10	2025	SAFT-CUSTOMERS	10.03.2026	07:11:26	PAVANK	/TROIC/DATA_RPRT_OIC	Inoast		200-Successful
2468	527	2810	11	2025	SAFT-CUSTOMERS	10.03.2026	07:12:27	PAVANK	/TROIC/DATA_RPRT_OIC	DELETE	DELETE	200-Successful
2469	730	2810	11	2025	SAFT-CUSTOMERS	10.03.2026	07:12:27	PAVANK	/TROIC/DATA_RPRT_OIC	Placeholder		202-Successful
2470	730	2810	11	2025	SAFT-CUSTOMERS	10.03.2026	07:12:27	PAVANK	/TROIC/DATA_RPRT_OIC	Upload		200-Successful
2471	730	2810	11	2025	SAFT-CUSTOMERS	10.03.2026	07:12:33	PAVANK	/TROIC/DATA_RPRT_OIC	Inoast		200-Successful
2472	731	2810	12	2025	SAFT-CUSTOMERS	10.03.2026	07:12:33	PAVANK	/TROIC/DATA_RPRT_OIC	Placeholder		202-Successful
2473	731	2810	12	2025	SAFT-CUSTOMERS	10.03.2026	07:13:34	PAVANK	/TROIC/DATA_RPRT_OIC	Upload		200-Successful
2474	731	2810	12	2025	SAFT-CUSTOMERS	10.03.2026	07:13:39	PAVANK	/TROIC/DATA_RPRT_OIC	Inoast		200-Successful

NOTE

The format for currency fields is sent as per below in the export file/CSV:

- Thousand Separator as Comma (,)
- Decimal Separator as Dot (.)

Import status

Import status can be obtained by selecting the 'Import status' radio button on the selection screen and entering the corresponding import ID.

OIC Data Transfer

Execution Type

☐ Report

☒ Import status

Import ID to

NOTE: The same 'Status' Call Type is updated with the latest status for that specific import ID each time the import status is executed.

Log viewer

You can also view the logs of each call made to OIC, using tcode: /N/TROIC/LOG or directly from the OIC user menu.

Users can filter specific logs using selection parameters within the log report.

Log Report

Selection Parameters

Log Counter		to		
Current Date	10.03.2026	to		
Import ID		to		
Company Code		to		
Posting period		to		
Fiscal Year		to		
Report Type		to		
User Name	PAVANK	to		
Import Status				
Program Name		to		

On execution, the below screen is displayed where users can access the JSON response for each call made to OIC.

Log Report

Log Co...	Imp ID	CoCo...	Peri...	Fiscal...	Report Type	Date	Time	User	Program name	Call Type	Imp Status	OIC Comm
2454	571	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:07:31	PAVANK	/TROIC/DATA RPRT OIC	DELETE	DELETE	200-Successful
2455	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:42	PAVANK	/TROIC/DATA RPRT OIC	Placeholder		202-Successful
2456	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:46	PAVANK	/TROIC/DATA RPRT OIC	Upload		200-Successful
2457	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:55	PAVANK	/TROIC/DATA RPRT OIC	Ingest		200-Successful
2458	727	2810	11	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:58	PAVANK	/TROIC/DATA RPRT OIC	Placeholder		202-Successful
2459	727	2810	11	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:03	PAVANK	/TROIC/DATA RPRT OIC	Upload		200-Successful
2460	727	2810	11	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:09	PAVANK	/TROIC/DATA RPRT OIC	Ingest		200-Successful
2461	563	2810	12	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:10	PAVANK	/TROIC/DATA RPRT OIC	DELETE	DELETE	200-Successful
2462	728	2810	12	2025	SAFT-GL ACCOUNTS	10.03.2026	07:10:11	PAVANK	/TROIC/DATA RPRT OIC	Placeholder		202-Successful

Log Report

Log Co...	Imp ID	CoCo...	Peri...	Fiscal...	Report Type	Date	Time	User	Program name	Call Type	Imp Status	OIC Comm
2454	571	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:07:31	PAVANK	/TROIC/DATA RPRT OIC	DELETE	DELETE	200-Successful
2455	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:42	PAVANK	/TROIC/DATA RPRT OIC	Placeholder		202-Successful
2456	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:46	PAVANK	/TROIC/DATA RPRT OIC	Upload		200-Successful
2457	726	2810	10	2025	SAFT-GL ACCOUNTS	10.03.2026	07:08:55	PAVANK	/TROIC/DATA RPRT OIC	Ingest		200-Successful

24 Output

```

24 {
24   "id":726,
24   "status":"QueuedForImport",
24   "error-message":null,
24   "has-errors":false
24 }
24
24
24
24

```

'OIC Communication status' indicates the response code for each call made from SAP to OIC. On the other hand, 'Import Status' reflects the status of the import file sent to OIC.

Customize using field mapping

Users have the flexibility to utilize the field mapping framework, in case any customizations are needed. You can either override an existing field mapping or add a new field in the communication structure.

Highest sort order takes precedence in case of multiple entries with the same target field and company code.

In the example below, a new field mapping is added to the communication structure.

New Entries: Overview of Added Entries

Maintain Dynamic Field Mapping

Standard	Product	Report Type	Country	Sort Order	Active	CoCd	Source Base	Source Field	Target Field	Comments
☒	OIC	SAFT-GL ACCOUNTS	RO	000010	☒	*	SRB1	BUKRS	ENTITY CODE	DIRECT FIELD
☐					☐					

A new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC_GLT)

when using Data Set - G/L Transactions.

Dictionary: Display Structure

</

If you are using CALC_BSEG OR CALC_BSET to customize the field mapping, make sure these structures have the desired source fields. If you cannot make use of existing fields in these structures, you can append your own fields to these structures.

NOTE

Implement BADIs if the customization is made to the CALC_BSEG OR CALC_BSET fields.

A new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC_INTRASTAT)

when using INTRASTAT.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_INTRASTAT Active

Short Description: Target structure for OIC Intrastat

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 22

Component	Typing Method	Component Type	Data Type	Length	Decimal...	Coordinate	S
CUSTOMERVATNUMBE	Types	/TROIC/STRING	STRING	0	0		0 Si
DESTINATIONJURIS	Types	/TROIC/STRING	STRING	0	0		0 Si
DESTINATIONREGIO	Types	/TROIC/STRING	STRING	0	0		0 Si
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 Si
FLOW	Types	/TROIC/STRING	STRING	0	0		0 Si
GOODSDESCRIPTION	Types	/TROIC/STRING	STRING	0	0		0 Si
MODETRANSPORT	Types	/TROIC/STRING	STRING	0	0		0 Si
NATURETRANSACTION	Types	/TROIC/STRING	STRING	0	0		0 Si
ORIGINARRIVALJUR	Types	/TROIC/STRING	STRING	0	0		0 Si
ORIGINJURISDICTION	Types	/TROIC/STRING	STRING	0	0		0 Si
ORIGINREGIONDISP	Types	/TROIC/STRING	STRING	0	0		0 Si
PORTLOADING	Types	/TROIC/STRING	STRING	0	0		0 Si
PORTUNLOADING	Types	/TROIC/STRING	STRING	0	0		0 Si

If you are using CALC_RPHD OR CALC_RPIT to customize the field mapping, make sure these structures have the desired source fields. If you cannot make use of existing fields in these structures, you can append your own fields to these structures.

Along with this, a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset - GLA**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_GLA Active

Short Description: Target structure for OIC SAFT GLA

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 13

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ACCOUNTID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ACCOUNTDESCRIP...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STANDARDACCOUNT...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
GROUPINGCATEGORY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
GROUPINGCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ACCOUNTTYPE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ACCOUNTCREATION...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
OPENINGDEBIT	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
OPENINGCREDIT	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CLOSINGDEBIT	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CLOSINGCREDIT	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -CUS**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_CUS Active

Short Description: Target structure for OIC SAFT CUSTOMER

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 41

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REGISTRATIONNUM...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CUSTOMERNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STREETNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STREETNUMBER	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ADDITIONALADDRE...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
BUILDING	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CITY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
POSTALCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REGION	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
COUNTRY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ADDRESSTYPE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TITLE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
FIRSTNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
INITIALS	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PREFIX	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
LASTNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset – SUP.**

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_SUP Active
Short Description: Target structure for OIC SAFT SUPPLIERS

Attributes Components Input Help/Check Currency/quantity fields

1 / 41

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REGISTRATIONNUM...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
SUPPLIERNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STREETNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STREETNUMBER	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ADDITIONALADDRE...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
BUILDING	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CITY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
POSTALCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REGION	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
COUNTRY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ADDRESSTYPE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TITLE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
FIRSTNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
INITIALS	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PREFIX	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
LASTNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -AST.**

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_AST Active
Short Description: Target structure for OIC SAFT Assets

Attributes Components Input Help/Check Currency/quantity fields

1 / 38

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ASSETID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ACCOUNTID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
DESCRIPTION	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
SUPPLIERNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
SUPPLIERID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STREETNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STREETNUMBER	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ADDITIONALADDRE...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
BUILDING	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CITY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
POSTALCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REGION	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
COUNTRY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ADDRESSTYPE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PURCHASEORDERDA...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
DATEOFACQUISITI...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -UOM**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_UOM Active

Short Description: Target structure for OIC SAFT UOM

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 4

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
UNITOFMEASURE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
UOMDESCRIPTION	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -TAX**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_TAX Active

Short Description: Target Structure for OIC SAFT Tax Table

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 16

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TAXTYPE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TAXTYPEDESCRIPT...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TAXCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
EFFECTIVEDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
EXPIRATIONDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TAXCODEDESCRIPT...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TAXPERCENTAGE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
AMOUNT	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CURRENCYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CURRENCYAMOUNT	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
EXCHANGERATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
BASERATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
COUNTRY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REGION	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset - ATT**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_ATT Active
 Short Description: Target structure for OIC SAFT Analysis TypeTable

Attributes Components Input Help/Check Currency/quantity fields

1 / 6

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ANALYSISTYPE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ANALYSISTYPEDES...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ANALYSISID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ANALYSISIDDESCR...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset - MTT**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_MTT Active
 Short Description: Target Structure for OIC SAFT Movement Type Table

Attributes Components Input Help/Check Currency/quantity fields

1 / 4

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
MOVEMENTTYPE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
MOVEMENTSUBTYPE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -PRD.**

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_PRD Active

Short Description: Target structure for OIC SAFT Products

Attributes Components Input Help/Check Currency/quantity fields

1 / 14

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PRODUCTCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
GOODSSERVICESID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PRODUCTGROUP	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PRODUCTDESCRIP...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PRODUCTCOMMODIT...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PRODUCTNUMBERCO...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
VALUATIONMETHOD	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
UOMBASE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
UOMSTANDARD	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
UOMTOUOMBASECON...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TAXTYPE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TAXCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -PST.**

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_PST Active

Short Description: Target Structure for OIC SAFT Physical Stock

Attributes Components Input Help/Check Currency/quantity fields

1 / 19

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
WAREHOUSE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
LOCATIONID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
GOODSCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STOCKACCOUNTINGO...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PRODUCTTYPE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PRODUCTSTATUS	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STOCKACCOUNTCOM...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
OWNERID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
UOMPHYSICALSTOCK	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
UOMTOUOMBASECON...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PRICE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
OPENINGSTOCKQUA...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
OPENINGSTOCKVAL...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CLOSINGSTOCKQUA...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CLOSINGSTOCKVAL...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STOCKCHARACTERI...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -OWN**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_OWN Active
Short Description: Target Structure for OIC SAFT Owners

Attributes Components Input Help/Check Currency/quantity fields

1 / 36

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REGISTRATIONNUM...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
OWNERNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STREETNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
STREETNUMBER	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ADDITIONALADDRE...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
BUILDINGNUMBER	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CITY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
POSTALCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REGION	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
COUNTRY	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
ADDRESSTYPE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
TITLE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
FIRSTNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
INITIALS	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
PREFIX	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
LASTNAME	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -GLE**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_GLE Active
Short Description: Target Structure for OIC SAFT General Ledger Entries

Attributes Components Input Help/Check Currency/quantity fields

1 / 50

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
JOURNALID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
JOURNALDESCRIP...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
JOURNALGROUPING...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
INVOICEID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGMONTH	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
REPORTINGYEAR	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
INVOICEDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
SOURCEID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
JOURNALTRANSACTION...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
JOURNALTRANSACTION...	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
BATCHID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
SYSTEMENTRYDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
POSTINGDATE	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
CUSTOMERID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
SUPPLIERID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects
SYSTEMID	Types	/TROIC/STRING	STRING	0	0		0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset - SIN**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAF_SIN Active
 Short Description: Target structure for OIC SAFT Sales Invoices

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 147

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
INVOICENO	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERNAME	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERSTREETN...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERNUMBER	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERADDITIO...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERBUILDING	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERCITY	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERPOSTALC...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERREGION	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERCOUNTRY	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERADDRESS...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ACCOUNTID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
BRANCHSTORENUMB...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
PERIOD	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
PERIODYEAR	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset - PIN**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFI_PIN Active
Short Description: Target structure for OIC SAFI Purchase Invoices

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 147

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
INVOICENO	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERNAME	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERSTREETN...	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERNUMBER	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERADDITIO...	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERBUILDING	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERCITY	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERPOSTALC...	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERREGION	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERCOUNTRY	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SUPPLIERADDRESS...	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ACCOUNTID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
BRANCHSTORENUMB...	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
PERIOD	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
PERIODYEAR	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset - PAY**.

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFI_PAY Active
Short Description: Target Structure for OIC SAFI Payments

Attributes Components Input Help/Check Currency/quantity fields

Built-In Type 1 / 49

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
PAYMENTREFNO	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
PERIOD	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
PERIODYEAR	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
TRANSACTIONID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
TRANSACTIONDATE	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
PAYMENTTYPE	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
DESCRIPTION	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
BATCHID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SYSTEMID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SOURCEID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ORIGINALINENUM...	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
SOURCEDOCUMENTID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ACCOUNTID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ANALYSISTYPE	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ANALYSISID	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects
ANALYSISAMOUNT	Types	/TROIC/STRING	STRING	0	0	0	0 String Data Element used for OIC objects

If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset -ATR.**

Structure

/TROIC/TARGET_OIC_SAFT_ATR

Active

Short Description

Target Structure for OIC SAFT Asset Transactions

Attributes

Components

Input Help/Check

Currency/quantity fields



Built-In Type

1 / 24

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
REPORTINGDATE	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
NUMBEROFASSETTR...	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ASSETTRANSACTION...	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ASSETID	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ASSETTRANSACTION...	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
DESCRIPTION	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ASSETTRANSACTION...	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
SUPPLIERNAME	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
SUPPLIERID	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
STREETNAME	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
NUMBER	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ADDITIONALADDRE...	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
BUILDING	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CITY	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
POSTALCODE	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
REGION	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
COUNTRY	Types	▼ /TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects



If a new target field has to be appended to the back-end communication structure (/TROIC/TARGET_OIC)

when using **SAFT Dataset - MVG.**

Dictionary: Display Structure

Structure: /TROIC/TARGET_OIC_SAFT_MVG Active
 Short Description: Target Structure for OIC SAFT Movement Of Goods

Attributes Components Input Help/Check Currency/quantity fields

1 / 65

Component	Typing Method	Component Type	Data Type	Length	Deci...	Coordinate	Short Description
ENTITYCODE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
REPORTINGDATE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
MOVEMENTREFEREN...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
MOVEMENTDATE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
MOVEMENTPOSTING...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
MOVEMENTPOSTING...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
TAXPOINTDATE2	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
MOVEMENTTYPE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
SOURCEID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
SYSTEMID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
DOCUMENTTYPE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
DOCUMENTNUMBER	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
DOCUMENTLINE	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ORIGINALLINENUM...	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
ACCOUNTID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
TRANSACTIONID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
CUSTOMERID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects
SUPPLIERID	Types	/TROIC/STRING	STRING	0	0	0	String Data Element used for OIC objects

OIC General Configuration for Field Separator

This manual provides step-by-step instructions for configuring and maintaining the OIC (OneSource Indirect Tax Compliance) integration with General Setup, with the respective values, field separators, and amount field handling in SAP so as to generate the output csv correctly with the required field separators, and the conversion of the amount fields format are recognized and converted by the integration with required formats so as to match the setup in OIC.

If both lines are active, highest sort order takes precedence for the same username.

Note: Amount field values for few currency/countries have different SAP internal format than SAP display format. Hence conversion of the amount fields is implemented as part of General configuration.

1. Accessing the OIC General Configuration

Transaction Code: /TROIC/GENERAL

1. Log in to SAP.
2. Enter transaction code /TROIC/GENERAL in the command field.
3. Press Enter to open the OIC General Configuration screen.

Change View "OIC General Configuration": Overview				
New Entries				
OIC General Configuration				
Sort Order	General Option	Value	Active	
000001	CSV SEPARATOR		☒	
000002	AMOUNT FIELD	FWSTE	☒	
000003	AMOUNT FIELD	FWBAS	☒	
000004	AMOUNT FIELD	INVAL	☒	
000005	AMOUNT FIELD	GROSS_AMT	☒	
000006	API WAIT DURATION (Seconds)	5	☒	

2. Setting up Sort Orders and Field Separators

Purpose: Sort Orders shown above define the primary interpretation for the precedence and execution order of tax rules and settings, which directly impacts the accuracy of tax calculations and also formatting of fields in the OIC file output. The field separator determines how columns are separated in the CSV output file.

Steps:

- On the OIC General Configuration screen, locate the Sort Orders section.
- As in above screen, Column General option with value "CSV Separator" is maintained with value; (Pipe Operator) is used to define the field separator for the CSV file output.
 - By default, the separator is set to a semicolon (|)
 - Users can maintain separator according to their necessity, to change the separator:
 - Edit the separator value to your preferred character (e.g., **(comma)** or \t **(tab)**, etc.) and make sure the "Active" checkbox is checked.
 - Inform the OIC team of the new separator so it can be updated in the OIC import specification configuration.
 - If multiple separators are maintained, the system will consider whichever is maintained in the OIC general configuration, it will select the first active one.
- Save your changes.

NOTE: The chosen separator will be used as a column in the generated CSV file output and at OIC.

3. Configuring Amount Fields for SAP Display

Purpose: Rows with Amount field have values with Amount field names maintained referring to the amount fields from SAP tables which we use in the OIC. These ensure

that amounts are displayed in SAP's specific standard format, converting internal SAP values to SAP display values.

Example:

- In the SAP document display (e.g., FB03), a tax value might show as 250 for CLP currency.
- In the SAP table BSET for e.g. currency CLP, it is stored as 2.5 (SAP internal format).
- The configuration ensures 2.5 is converted to 250 for SAP display format.

Steps:

1. Users can add new amount-specific fields in the field mapping:
 - a. Ensure to add the same field in the OIC General table, refer to screen shot above.
 - b. This maintains consistency and correct conversion for SAP display.

4. Maintenance & Best Practices

- The same set up above needs to be maintained in OIC to recognize the field separator in the file.
- When adding new amount fields, update both the field mapping (T.Code: /TROIC/FIELD_MAP) and the OIC General table (T.Code: /TROIC/GENERAL)

5. Troubleshooting

- CSV Output Issues: If columns are not separated as expected, verify the field separator in Colum General option with value "CSV Separator" from the above screen.
- Amount Display Issues: If amounts appear in incorrect format, check that all relevant amount fields are correctly mapped in field mapping and maintained in the OIC General table.

FREQUENTLY ASKED QUESTIONS

Is the Integration compatible with SAP S/4HANA?

Yes.

Which S/4HANA versions are the Integration supported on?

This integration has been tested to be compatible with S/4HANA 2021 & support pack stack (SPS) 6 and onwards.

Is integration compatible with ECC?

For this integration to work with SAP ECC, a review of the field mapping and core object customization is required.

How many transactions can be processed on one csv file?

This solely depends on the customer's infrastructure and the resources allotted in that particular SAP landscape.

What are the report types supported for this integration?

Though standard field mappings are provided for VAT-ESL, G/L Transactions, INTRASTAT , SAF-T reports.

Users have the flexibility to customize the standard mappings and can be extended to other reports

by generating new TR transports that may require ABAP coding, field mapping for required data,

use of BADIs, and enhancement of current selection screens.

Are Multiple Field separators supported?

Only a single delimiter character can be specified per CSV file configuration, Multiple delimiter characters cannot be used together in the same file processing operation, hence multiple field separators are not Supported.