# LiveNote™ Stream Manager™: Setting Options

Stream Manager and CAT Software on Same Computer: Using a Serial Connection and the Internet (Recommended)

- Stream Manager and CAT software are installed on the same computer.

- One participant is connecting from the deposition using a serial cable.

- One participant is connecting from a remote site using the Internet.

Court reporter

Serial cable   Internet

Participant at deposition using LiveNote software

Participant at remote site using the Internet

You must access the CAT system and LiveNote Stream in the following order:

1. Access the CAT system.
2. Note the baud rate and COM port number that are used for the session.
3. Close the CAT system.
4. Access LiveNote Stream.
5. Set the options in the Realtime Options dialog box as shown below.
6. Re-access the CAT system.

A Click **Local CAT System** when Stream Manager and CAT software are installed on the same computer.

B In the **CAT Output** list, click **CaseView**.

C In the **Baud Rate** list, click the same rate that is set in the CAT system.

D In the **CAT sending on** list, click the same COM port that is set in the CAT system.

E Do **not** click the Use Virtual Port check box when a participant is using a serial cable.

THOMSON REUTERS®

Stream Manager and CAT Software on Same Computer: Using Internet Connections Only

- Stream Manager and CAT software are installed on the same computer.

- One participant is connecting from the deposition via the Internet using Westlaw Case Notebook or LiveNote software.

- One participant is connecting from a remote site using the Internet.

Court reporter with
Stream Manager and CAT

Internet

Internet

Participant at deposition
using software

Participant at remote
site using the Internet

Access LiveNote Stream before you access the CAT system. Set the options in the Realtime Options dialog box as shown below:

A Click **Local CAT System** when Stream Manager and CAT software are installed on the same computer.

B In the **CAT Output** list, click **CaseView**.

C In the **Baud Rate** list, click the same rate that is set in the CAT system.

D Stream Manager automatically chooses the COM port. Set your CAT software's Output field to the same COM port displayed in the CAT sending on box.

E Select the **Use Virtual Port** check box when all participants are using the Internet.

Stream Manager and CAT Software on Separate Computers: Using a Serial Connection and the Internet

If you are using Stenocast or wireless equipment, Stream Manager and CAT software must be installed on separate computers, as described below.

- Stream Manager and CAT software are installed on separate computers.

- One participant is connecting from the deposition using a serial connection.

- One participant is connecting from a remote site using the Internet.

CAT software → Multi-line Block → Stream Manager

Serial connection

Internet

Participant at deposition using software

Participant at a remote site using the Internet

Set the options in the Realtime Options dialog box as shown below:

A Click **Serial** when Stream Manager and CAT software are installed on separate computers.

B In the **CAT Output** list, click **CaseView**.

C In the **Baud Rate** list, click the same rate that is set in the CAT system.

D In the **Serial Port** list, click the same COM port that is set in the Stream Manager computer receiving the real-time feed.

THOMSON REUTERS®